MUNI

HCI LAB

PA199
Advanced Game Design

Lecture 3
Mathematics for Game Design

Dr. Fotis Liarokapis

28th February 2020

Basis and Coordinate Systems

- In any scene, we need a way to be able to position and orientate points, vectors, objects, etc:
  - We do this be defining a basis
- The basis is defined by an origin and a number of basis vectors
  - Can think of the basis as a 'starting point'
- We employ a Cartesian basis

HCI LAB

Basis and Coordinate Systems .

- The basis vectors are mutually orthogonal and unit length
  - Unit length:
    - Have a length of 1
  - Mutually Orthogonal:
    - Each vector is at a right angle to the others
- Basis vectors for 3 dimensions
  - Use 'x' and 'y' for 2 dimensions
  - Position in Cartesian coordinates specified by (x, y, z)

HCI LAB

Left-handed vs. Right-Handed

OpenGL is right handed in object space and world space

But in window space (screen space) left handed

left handed
Z axis goes "into" the page

right handed
Z axis goes "out" of the page

HCI LAB


Local Coordinate System

- Preferred system for construction of object parts
- 3D Cartesian system
- Object vertices centered about the local origin

HCI LAB

3D World Coordinate System

- 3D Cartesian coordinate system
- Arbitrary centre, handedness and orientation
- Used in the construction stage

HCI LAB

Camera Coordinate System

- Used to define the view onto the 3D world that the user will see on the screen
- Centre (0,0,0) is located at the Imaginary User's eye
- Axes oriented such that:
  - One indicates the direction in which the user looks
  - The second indicates roughly the 'up' direction
  - The third indicates the handedness

HCl LAB

## Example of Camera Coordinate System

OpenGL: see gluLookAt

https://www.opengl.org/sdk/docs/man2/xhtml/gluLookAt.xml

HCl LAB

3D Camera Viewing

- Note that the following scenes should produce the same image

SCENE 1   SCENE 2

- In 'Scene 2', relative position of objects and camera remain constant but the actually scene has been changed
  - It has been transformed

HCl LAB

Notation: Scalars, Vectors, Matrices

- Scalar a
  - Lower case, italic
- Vector $\mathbf{a} = \begin{bmatrix} a_1 & a_2 & \dots & a_n \end{bmatrix}$
  - Lower case, bold
- Matrix
  - Upper case, bold

$$\mathbf{A} = \begin{bmatrix} a_{11} & a_{12} & a_{13} \\ a_{21} & a_{22} & a_{23} \\ a_{31} & a_{32} & a_{33} \end{bmatrix}$$

HCl LAB

Vectors

- A quantity characterized by a **magnitude** and **direction**
  - Can be represented by an arrow, where **magnitude** is the length of the arrow and the **direction** is given by slope of the line

$\mathbf{v} = \begin{bmatrix} 2 \\ 1 \end{bmatrix}$

$\mathbf{v} = \begin{bmatrix} 2 \\ 2 \\ 2 \end{bmatrix}$

A vector in 2D   A vector in 3D

HCl LAB

Vectors in 3D Co-ordinates

Right Handed Co-ordinate System   Left Handed Co-ordinate System

$\mathbf{v} = \begin{bmatrix} 0.5 \\ 0.7 \\ 0.5 \end{bmatrix} = \begin{bmatrix} 0.5 \\ 0.7 \\ -0.5 \end{bmatrix}$

RHS   LHS

HCl LAB

Vector Subtraction

Can be seen as an addition of

u + (**-1v**)

$$\begin{bmatrix}1\\4\end{bmatrix} - \begin{bmatrix}5\\2\end{bmatrix} = \begin{bmatrix}-4\\2\end{bmatrix}$$

HCI LAB

Vector Magnitude

- The magnitude or "norm" of a vector of dimension n is given by the standard Euclidean distance metric:

$$\|\mathbf{v}\| = \sqrt{v_1^2 + v_2^2 + \Lambda + v_n^2}$$

HCI LAB

Vectors for Direction

- Vectors represent
  - Direction
  - Magnitude
- In games can be used for representing:
  - Position
  - Velocity
 - Forces / impulses

HCI LAB

Example Vectors for Direction

- Describing velocity (direction and speed) of roller coaster and ball at different points in time

HCI LAB

Other Vectors

The forces of flight

Mesh Normals

HCI LAB

## Vertices and Points

- Vectors can however communicate a position
- Referred to as a point or vertex
- A vertex is actually represented by its displacement from the origin { 0, 0, 0 }

$$\mathbf{v} = \begin{bmatrix}v_x\\v_y\end{bmatrix} \quad \mathbf{P} = \begin{bmatrix}v_x\\v_y\end{bmatrix}$$

both vectors equal

With the origin O, we can use this to represent a unique position in space

HCI LAB

Unit Vectors

- Vectors of length 1 are often termed unit vectors
  - Normalised vectors
- When we only wish to describe direction we use normalised vectors
  - Often to avoid redundancy
- For this (and other reasons), we often need to normalise a vector: $\hat{\mathbf{v}} = \dfrac{\mathbf{v}}{\|\mathbf{v}\|} = \dfrac{1}{\sqrt{v_1^2 + v_2^2 + \Lambda + v_n^2}}\,\mathbf{v}$

HCI LAB

Dot Product Definition

- Dot product (inner product) is defined as:

$$\mathbf{u}\cdot\mathbf{v} = \sum_i u_i v_i$$

$$\mathbf{u}\cdot\mathbf{v} = \begin{bmatrix} u_1 \\ u_2 \end{bmatrix}\begin{bmatrix} v_1 \\ v_2 \end{bmatrix} = u_1 v_1 + u_2 v_2$$

$$\mathbf{u}\cdot\mathbf{v} = \begin{bmatrix} u_1 \\ u_2 \\ u_3 \end{bmatrix}\begin{bmatrix} v_1 \\ v_2 \\ v_3 \end{bmatrix} = u_1 v_1 + u_2 v_2 + u_3 v_3$$

HCI LAB

Dot Product Magnitude

- Therefore we can redefine magnitude in terms of the dot-product operator:

$$\mathbf{u}\cdot\mathbf{u} = u_1^2 + u_2^2 + u_3^2 = \|\mathbf{u}\|^2 \quad\Longrightarrow\quad \|\mathbf{u}\| = \sqrt{\mathbf{u}\cdot\mathbf{u}}$$

- Note that the dot product operator is **commutative** and **associative**
  - Changing the order of the operands does not change the result
 - (x * y) * z = x * (y * z)

HCI LAB

Dot Product Using Angle

- The Dot Product can also be obtained from the following equation:

$$\mathbf{u}\cdot\mathbf{v} = \|\mathbf{u}\|\|\mathbf{v}\|\cos\theta$$

- where θ is the **angle** between the two vectors

HCI LAB

Angle Between Two Vectors

- So, if we know the vectors u and v, then the dot product is useful for finding the angle between two vectors:

$$\mathbf{u}\cdot\mathbf{v} = \|\mathbf{u}\|\|\mathbf{v}\|\cos\theta \quad\Rightarrow\quad \theta = \cos^{-1}\left[\dfrac{\mathbf{u}\cdot\mathbf{v}}{\|\mathbf{u}\|\|\mathbf{v}\|}\right]$$

- Note that if we had already normalised the vectors u and v then it would simply be:

$$\theta = \cos^{-1}[\hat{\mathbf{u}}\bullet\hat{\mathbf{v}}]$$

HCI LAB

Dot Product Special Case

- If both vectors are normal, the dot product defines the cosine of the angle between the vectors:

$$\mathbf{u}\cdot\mathbf{v} = \cos\theta$$

But in general:

$$\mathbf{u}\cdot\mathbf{v} = \|\mathbf{u}\|\|\mathbf{v}\|\cos\theta$$

$$\Rightarrow \theta = \cos^{-1}\left[\dfrac{\mathbf{u}\cdot\mathbf{v}}{\|\mathbf{u}\|\|\mathbf{v}\|}\right]$$

if θ > 90 then the dot product is negative

HCI LAB

Projection Using Dot Product

- Can find length of projection of u onto v

$$\mathbf{u} \bullet \mathbf{v} = \|\mathbf{u}\|\|\mathbf{v}\|\cos\theta$$

$$\|\mathbf{u}\|\cos\theta = \frac{\mathbf{u} \bullet \mathbf{v}}{\|\mathbf{v}\|}$$

- As lines become perpendicular:


HCI LAB

Cross Product

- Used for defining **orientation** and constructing **co-ordinate axes**
- Cross product defined as:

$$\mathbf{u} \times \mathbf{v} = \begin{bmatrix} u_1 \\ u_2 \\ u_3 \end{bmatrix} \times \begin{bmatrix} v_1 \\ v_2 \\ v_3 \end{bmatrix} = \begin{bmatrix} u_2 v_3 - u_3 v_2 \\ u_3 v_1 - u_1 v_3 \\ u_1 v_2 - u_2 v_1 \end{bmatrix}$$

- The result is a vector, perpendicular to the plane defined by **u** and **v**:

$$\mathbf{u} \times \mathbf{v} = \mathbf{w} \|\mathbf{u}\|\|\mathbf{v}\|\sin\theta$$

HCI LAB

Cross Product Examples

Plane defined by the span of vectors **u**,**v**

cross product direction

rotation direction

Right Handed Coordinate System

HCI LAB

## Cross Product Properties

- Cross product is **anti-commutative**:

$$\mathbf{u} \times \mathbf{v} = -(\mathbf{v} \times \mathbf{u})$$

- It is **not associative**:

$$\mathbf{u} \times (\mathbf{v} \times \mathbf{w}) \neq (\mathbf{u} \times \mathbf{v}) \times \mathbf{w}$$

- Direction of resulting vector defined by operand order:

Anti-clockwise Rotation

Clockwise Rotation

HCI LAB

Vector Class

```
class TVector {
    public:
        double _x, _y, _z;

        // Constructors
        TVector(double x, double y, double z, TStatus s) : _x(x),   _y(y),
        _z(z), _Status(s) {}
        TVector(double x, double y, double z) : _x(x), _y(y),       _z(z),
        _Status(DEFAULT) {}

        // Functions here

};
#endif
```

HCI LAB

Vector Subtraction Example

```
TVector &TVector::subtract(const TVector &v1, const TVector
    &v2, TVector &result)
{
    if (v1.isValid() && v2.isValid())
    {
        result._x = v1._x - v2._x;
        result._y = v1._y - v2._y;
        result._z = v1._z - v2._z;
        result._Status = DEFAULT;
    } else
        result = TVector();
    return result;
}
```

HCI LAB

What is a Matrix?

- A matrix is a set of elements, organized into rows (m) and columns (n)

$$
\begin{matrix}
\text{Rows,} \\
i = 1, \ldots, m
\end{matrix}
\left\{
\begin{pmatrix}
a_{11} & a_{12} & a_{13} & \Lambda & a_{1n} \\
a_{21} & a_{22} & a_{23} & & a_{2n} \\
M & & & O & M \\
a_{m1} & a_{m2} & a_{m3} & K & a_{mn}
\end{pmatrix}
\right.
$$

Columns,
$j = 1, \ldots, n$

HCI LAB

Why Use Matrices?

- Variety of engineering problems lead to the need to solve systems of linear equations

$$Ax = b$$

$$
A = \begin{pmatrix}
a_{11} & a_{12} & a_{13} & \Lambda & a_{1n} \\
a_{21} & a_{22} & a_{23} & & a_{2n} \\
M & & & O & M \\
a_{m1} & a_{m2} & a_{m3} & K & a_{mn}
\end{pmatrix}
\quad
x = \begin{pmatrix}
x_1 \\ x_2 \\ M \\ x_n
\end{pmatrix}
\quad
b = \begin{pmatrix}
b_1 \\ b_2 \\ M \\ b_m
\end{pmatrix}
$$

matrix   **column vectors**

HCI LAB

Row and Column Matrices (vectors)

- Row matrix (or row vector) is a matrix with one row

$$r = \begin{pmatrix} r_1 & r_2 & r_3 & \Lambda & r_n \end{pmatrix}$$

- Column vector is a matrix with only one column

$$c = \begin{pmatrix} c_1 \\ c_2 \\ M \\ c_m \end{pmatrix}$$

HCI LAB

Square Matrix

- When the row and column dimensions of a matrix are equal (m = n) then the matrix is called **square**

$$
A = \begin{pmatrix}
a_{11} & a_{12} & \Lambda & a_{1n} \\
a_{21} & a_{22} & & a_{2n} \\
M & & O & \\
a_{n1} & a_{n2} & \Lambda & a_{nn}
\end{pmatrix}
$$

HCI LAB

Matrix Transpose

- The transpose of the (m x n) matrix A is the (n x m) matrix formed by interchanging the rows and columns such that row i becomes column i of the **transposed** matrix

$$
A = \begin{pmatrix}
a_{11} & a_{12} & \Lambda & a_{1n} \\
a_{21} & a_{22} & & a_{2n} \\
M & & O & \\
a_{m1} & a_{m2} & K & a_{mn}
\end{pmatrix}
\quad
A^T = \begin{pmatrix}
a_{11} & a_{21} & \Lambda & a_{m1} \\
a_{12} & a_{22} & & a_{m2} \\
M & & O & \\
a_{1n} & a_{2n} & \Lambda & a_{mn}
\end{pmatrix}
$$

HCI LAB

Matrix Equality

- Two (m x n) matrices A and B are **equal** if and only if each of their elements are equal
- That is when:
  - A = B
- If and only if:
  - $a_{ij} = b_{ij}$
  - For i = 1,...,m & j = 1,...,n

HCI LAB

Matrix Addition General Format

$$\mathbf{A} + \mathbf{B} = \begin{pmatrix} a_{11} & a_{12} & \Lambda & a_{1n} \\ a_{21} & a_{22} & & a_{2n} \\ M & & O & M \\ a_{m1} & a_{m2} & K & a_{mn} \end{pmatrix} + \begin{pmatrix} b_{11} & b_{12} & \Lambda & b_{1n} \\ b_{21} & b_{22} & & b_{2n} \\ M & & O & M \\ b_{m1} & b_{m2} & K & b_{mn} \end{pmatrix}$$

$$= \begin{pmatrix} a_{11} + b_{11} & a_{12} + b_{12} & \Lambda & a_{1n} + b_{1n} \\ a_{21} + b_{21} & a_{22} + b_{22} & & a_{2n} + b_{2n} \\ M & & O & M \\ a_{m1} + b_{m1} & a_{m2} + b_{m2} & K & a_{mn} + b_{mn} \end{pmatrix}$$

HCI LAB

Scalar Matrix Multiplication

- **Multiplication** of a matrix A by a **scalar** is defined as:

$$\alpha A = \begin{pmatrix} \alpha a_{11} & \alpha a_{12} & \Lambda & \alpha a_{1n} \\ \alpha a_{21} & \alpha a_{22} & & \alpha a_{2n} \\ M & & O & \\ \alpha a_{m1} & \alpha a_{m2} & K & \alpha a_{mn} \end{pmatrix}$$

HCI LAB

Matrix Multiplication with Matrix General Format

$$c_{ij} = \sum_{k=1}^{p} a_{ik} b_{kj}$$

$$C = AB = \begin{pmatrix} a_{11} & a_{12} & \Lambda & a_{1p} \\ a_{21} & a_{22} & & a_{1p} \\ M & & O & M \\ a_{m1} & a_{m2} & K & a_{mp} \end{pmatrix} \begin{pmatrix} b_{11} & b_{12} & \Lambda & b_{1n} \\ b_{21} & b_{22} & & b_{1n} \\ M & & O & M \\ b_{p1} & b_{p2} & K & b_{pn} \end{pmatrix}$$

$$= \begin{pmatrix} a_{1}b_{11} + \Lambda + a_{1p}b_{p1} & a_{1}b_{12} + \Lambda + a_{1p}b_{p2} & \Lambda & a_{1}b_{1n} + \Lambda + a_{1p}b_{pn} \\ a_{2}b_{11} + \Lambda + a_{2p}b_{p1} & a_{2}b_{12} + \Lambda + a_{2p}b_{p2} & & a_{2}b_{1n} + \Lambda + a_{2p}b_{pn} \\ M & & O & M \\ a_{m1}b_{11} + \Lambda + a_{mp}b_{p1} & a_{m1}b_{12} + \Lambda + a_{mp}b_{p2} & K & a_{m1}b_{1n} + \Lambda + a_{mp}b_{pn} \end{pmatrix}$$

HCI LAB

Diagonal Matrices

- Simple diagonal Matrix

$$A = \begin{pmatrix} a_{11} & 0 & 0 & 0 \\ 0 & a_{22} & 0 & 0 \\ 0 & 0 & O & 0 \\ 0 & 0 & 0 & a_{nn} \end{pmatrix}$$

HCI LAB

Identity Matrix

- The identity matrix has the property that if A is a square matrix, then:

$$IA = AI = A$$

$$I = \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix}$$

HCI LAB

Matrix Inverse

- If A is an (n x n) square matrix and there is a matrix X with the property that:

$$AX = I$$

- X is defined to be the inverse of A and is denoted A^{-1}

$$AA^{-1} = I \qquad A^{-1}A = I$$

HCI LAB

Matrix Class

```
class TMatrix33
{
    public:
        double _Mx[3][3];

        // Constructors
        TMatrix33();
        TMatrix33(double Phi, double Theta, double Psi);
        TMatrix33(TVector& Axis,double Psi);

        // Functions here
};
#endif
```
HCI LAB

Matrix Addition

```
TMatrix33 &TMatrix33::add(const TMatrix33 &m1, const
    TMatrix33 &m2, TMatrix33 &result) {
    result._Mx[0][0] = m1._Mx[0][0] + m2._Mx[0][0];
    result._Mx[0][1] = m1._Mx[0][1] + m2._Mx[0][1];
    result._Mx[0][2] = m1._Mx[0][2] + m2._Mx[0][2];
    result._Mx[1][0] = m1._Mx[1][0] + m2._Mx[1][0];
    result._Mx[1][1] = m1._Mx[1][1] + m2._Mx[1][1];
    result._Mx[1][2] = m1._Mx[1][2] + m2._Mx[1][2];
    result._Mx[2][0] = m1._Mx[2][0] + m2._Mx[2][0];
    result._Mx[2][1] = m1._Mx[2][1] + m2._Mx[2][1];
    result._Mx[2][2] = m1._Mx[2][2] + m2._Mx[2][2];
    return result;
}
```
HCI LAB

Transformations

- Allow us to move, orientate and change the primitives in our scene
  - Move, Rotate, Stretch, Squash, Shear
- Represented as matrices, such as:
  - We can store a translation and a rotation in a matrix
  - When we apply this matrix to an object, it will be translated and rotated as specified by the matrix
- Two ways of understanding a transformation:
 - Object Transformation
  - Coordinate Transformation

HCI LAB

Object vs Coordinate Transformations

- Object Transformation
  - Alters the coordinates of each point according to some rule
  - The underlying coordinate system remains unchanged
- Coordinate Transformation
  - Produces a different coordinate system
  - Then represents all original points in this new system

HCI LAB

Examples

Affine Transformations Definition

- An affine transformation is any transformation that preserves:
  - Collinearity
    - i.e. All points lying on a line initially still lie on a line after transformation
  - Ratios of distances
    - i.e. The midpoint of a line segment remains the midpoint after transformation

HCI LAB

Elementary Transformations

Translation

Scaling

Rotation

Shearing

HCI LAB

Homogeneous Coordinates

- Introduced in mathematics:
  - For projections and drawings
  - Used in artillery, architecture
  - Used to be classified material (in the 1850s)
- Add a third coordinate, *w*
- A 2D point is a 3 coordinates vector:

$$\begin{bmatrix} x \\ y \\ w \end{bmatrix}$$

HCI LAB

Homogeneous Coordinates .

- Two points are equal if and only if:
  - $x'/w' = x/w$ and $y'/w' = y/w$
- $w=0$: points at infinity
  - Useful for projections and curve drawing
- Homogenize = divide by *w*
- Homogenized points:

$$\begin{bmatrix} x \\ y \\ 1 \end{bmatrix}$$

HCI LAB

Translations with Homogeneous

$$\begin{bmatrix} x' \\ y' \\ w' \end{bmatrix} = \begin{bmatrix} 1 & 0 & t_x \\ 0 & 1 & t_y \\ 0 & 0 & 1 \end{bmatrix}\begin{bmatrix} x \\ y \\ w \end{bmatrix}$$

$$\begin{cases} \frac{x'}{w'} = \frac{x}{w} + t_x \\ \frac{y'}{w'} = \frac{y}{w} + t_y \end{cases}$$

$$\begin{cases} x' = x + wt_x \\ y' = y + wt_y \\ w' = w \end{cases}$$

HCI LAB

Scaling with Homogeneous

$$\begin{bmatrix} x' \\ y' \\ w' \end{bmatrix} = \begin{bmatrix} s_x & 0 & 0 \\ 0 & s_y & 0 \\ 0 & 0 & 1 \end{bmatrix}\begin{bmatrix} x \\ y \\ w \end{bmatrix}$$

$$\begin{cases} \frac{x'}{w'} = s_x \frac{x}{w} \\ \frac{y'}{w'} = s_y \frac{y}{w} \end{cases}$$

$$\begin{cases} x' = s_x x \\ y' = s_y y \\ w' = w \end{cases}$$

HCI LAB

Rotation with Homogeneous

$$\begin{bmatrix} x' \\ y' \\ w' \end{bmatrix} = \begin{bmatrix} \cos\theta & -\sin\theta & 0 \\ \sin\theta & \cos\theta & 0 \\ 0 & 0 & 1 \end{bmatrix}\begin{bmatrix} x \\ y \\ w \end{bmatrix}$$

$$\begin{cases} \frac{x'}{w'} = \cos\theta\frac{x}{w} - \sin\theta\frac{y}{w} \\ \frac{y'}{w'} = \sin\theta\frac{x}{w} + \cos\theta\frac{y}{w} \end{cases}$$

$$\begin{cases} x' = \cos\theta x - \sin\theta y \\ y' = \sin\theta x + \cos\theta y \\ w' = w \end{cases}$$

HCI LAB

Composition of Transformations

- To compose transformations, multiply the matrices:
  - Composition of a rotation and a translation:
    M = **RT**
- All transformations can be expressed as matrices
  - Even transformations that are not translations, rotations and scaling

HCI LAB

Rotation Around a Point Q

- Rotation about a point Q:
  - translate Q to origin (T_Q),
  - rotate about origin (R_Θ)
  - translate back to Q (- T_Q).

$$P'=(-T_Q)R_\Theta T_Q P$$

HCI LAB

Beware!

- Matrix multiplication is *not* commutative
- The order of the transformations is vital
  - Rotation followed by translation is *very* different from translation followed by rotation
  - Careful with the order of the matrices!
- Small commutativity:
  - Rotation commute with rotation, translation with translation…

HCI LAB

Matrices in OpenGL

- To initialise a matrix in OpenGL:
  - glLoadIdentity()
  - This clears the currently selected OpenGL matrix to the identity matrix
- To select a matrix as the current matrix:
  - glMatrixMode(mode)
    - GL_MODELVIEW, GL_PROJECTION, GL_TEXTURE

$$\begin{bmatrix} 0 & 4 & 8 & 12 \\ 1 & 5 & 9 & 13 \\ 2 & 6 & 10 & 14 \\ 3 & 7 & 11 & 15 \end{bmatrix}$$

HCI LAB

How do we do this ?

- OpenGL does most of it for us !
  - OpenGL keeps a current matrix that allows us to orientate our primitives
    - This is known as the *model-view* matrix
  - All primitives placed are altered by the transformation stored in the model-view matrix
  - Model-view matrix acts as a state parameter; once set it remains until altered
    - Use calls such as *glTranslate()* to modify the current model-view matrix

HCI LAB

Translation

- Think of translations as 'moving' without rotating
- Translation only applies to points
  - Doesn't apply to vectors, since vectors are just directions

Translate along **y axis**

$$\begin{bmatrix} 1 & 0 & 0 & a \\ 0 & 1 & 0 & b \\ 0 & 0 & 1 & c \\ 0 & 0 & 0 & 1 \end{bmatrix}$$

Translation Displacement

- The translation displacement is written in the 12th, 13th, and 14th positions of our OpenGL matrix
- These correspond to the displacements in the x, y and z directions
  - So 12th position is the translation in the x direction

HCI LAB

The Translation Matrix

- Example: Translate the point (x,y,z) by a displacement (a,b,c):
  - Gives us our translated point (x+a, y+b, z+c)
- glTranslate(dx, dy, dz)
  - Translates by a displacement (dx, dy, dz)
  - Calling glTranslate() concatenates the specified translation to the current model-view matrix
  - Any primitives drawn after this will be modified by the specified translation


Translation Displacement

$$\begin{bmatrix} 1 & 0 & 0 & a \\ 0 & 1 & 0 & b \\ 0 & 0 & 1 & c \\ 0 & 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} x \\ y \\ z \\ 1 \end{bmatrix} = \begin{bmatrix} x+a \\ y+b \\ z+c \\ 1 \end{bmatrix}$$

Point to be translated

HCI LAB

Rotation

- Change the orientation of a primitive, without affecting its position
- Rotation applies to both points and vectors
  - Rotating a vector will change its direction
- Rotations are conducted anti-clockwise about the origin

rotation of 45° about the Z axis

HCI LAB

Rotation

- Remember:

  Sin a = Opp / Hyp
  Cos a = Adj / Hyp
  Tan a = Opp / Adj

$$\text{original } v = \begin{bmatrix} r \cos a \\ r \sin a \end{bmatrix}$$

$$\text{rotated } v = \begin{bmatrix} r \cos (a+b) \\ r \sin (a+b) \end{bmatrix}$$

HCI LAB

Rotation

- Derivation:
- Expanding (a + b) from log tables:
  - Rotated x = r cos a cos b − r sin a sin b
  - Rotated y = r cos a sin b + r sin a cos b
- But:
  - Original x = r cos a
  - Original y = r sin a
- So:
  - Rotated x = original x cos b − original y sin b
  - Rotated y = original x sin b + original y cos b
- Elements 0, 1, 2, 4, 5, 6, 8, 9, 10 define any rotations in our transformation matrix

Rotation

$$\begin{bmatrix} 0 & 4 & 8 & 12 \\ 1 & 5 & 9 & 13 \\ 2 & 6 & 10 & 14 \\ 3 & 7 & 11 & 15 \end{bmatrix}$$

HCI LAB

The Rotation Matrix

- Rotations around the: x-axis (Rx), y-axis (Ry) and z-axis (Rz)

$$R_x = \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & \cos\theta & -\sin\theta & 0 \\ 0 & \sin\theta & \cos\theta & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix} \quad R_y = \begin{bmatrix} \cos\theta & 0 & \sin\theta & 0 \\ 0 & 1 & 0 & 0 \\ -\sin\theta & 0 & \cos\theta & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix} \quad R_z = \begin{bmatrix} \cos\theta & -\sin\theta & 0 & 0 \\ \sin\theta & \cos\theta & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix}$$

- glRotatef(angle, vx, vy, vz)
  - Rotates around the axis (vx, vy, vz) by *angle* degrees
  - Calling glRotate() concatenates the specified rotate to the current model-view matrix
  - Any primitives drawn after this will be modified by the specified rotation

HCI LAB

Scaling

- Allows us to make primitives larger and smaller, without changing the vertex positions of the original

Original   scale all axes   scale Y axis

$$\begin{bmatrix} s_1 & 0 & 0 \\ 0 & s_2 & 0 \\ 0 & 0 & s_3 \end{bmatrix} \begin{bmatrix} x \\ y \\ z \end{bmatrix} = \begin{bmatrix} s_1 x \\ s_2 y \\ s_3 z \end{bmatrix}$$

- Elements 1, 6, 11 define scales in our transformation matrix:
- glScalef(sx, sy, sz)
  - Scale a scene by sx in the y axis, sy in the y axis and sz in the z axis
  - The default value for sx,sy,sz is (1.0,1.0,1.0), which doesn't scale a scene at all
  - Any primitives drawn after this will be modified by the specified scaling

HCI LAB

OpenGL Perspective Projection

- The call glFrustum(l, r, b, t, n, f) generates R, where:

$$R = \begin{bmatrix} \frac{2n}{r-l} & 0 & \frac{r+l}{r-l} & 0 \\ 0 & \frac{2n}{t-b} & \frac{t+b}{t-b} & 0 \\ 0 & 0 & \frac{-(f+n)}{f-n} & \frac{-2fn}{f-n} \\ 0 & 0 & -1 & 0 \end{bmatrix} \text{ and } R^{-1} = \begin{bmatrix} \frac{r-l}{2n} & 0 & 0 & \frac{r+l}{2n} \\ 0 & \frac{t-b}{2n} & 0 & \frac{t+b}{2n} \\ 0 & 0 & 0 & -1 \\ 0 & 0 & \frac{-(f-n)}{2fn} & \frac{f+n}{2fn} \end{bmatrix}$$

- **R** is defined as long as l x r, t x b, and n x f

HCI LAB

OpenGL Orthographic Projection

- The call glOrtho(l, r, b, t, n, f) generates R, where:

$$R = \begin{bmatrix} \frac{2}{r-l} & 0 & 0 & \frac{r+l}{r-l} \\ 0 & \frac{2}{t-b} & 0 & \frac{t+b}{t-b} \\ 0 & 0 & \frac{-2}{f-n} & \frac{f+n}{f-n} \\ 0 & 0 & 0 & 1 \end{bmatrix} \text{ and } R^{-1} = \begin{bmatrix} \frac{r-l}{2} & 0 & 0 & \frac{r+l}{2} \\ 0 & \frac{t-b}{2} & 0 & \frac{t+b}{2} \\ 0 & 0 & \frac{f-n}{-2} & \frac{n+f}{2} \\ 0 & 0 & 0 & 1 \end{bmatrix}$$

- R is defined as long as l x r, t x b, and n x f

HCI LAB

2D and 3D Lines

- In 2D, two different lines can either be
  - Parallel, meaning they never meet
  - May intersect at one and only one point
- In 3D (or more dimensions), lines may also be skew (meaning they don't meet) but also don't define a plane
- Two distinct planes intersect in at most one line
- Three or more points that lie on the same line are called collinear

HCI LAB

2D Line Equation

- Lines in a Cartesian plane can be described algebraically by
  - Linear equations and functions
- In 2D the characteristic equation is often given by the slope-intercept form:
  - y = mx + b
- where:
  - m is the slope of the line
  - b is the y-intercept of the line
  - x is the independent variable of the function y

HCI LAB

Slope Definition

- Slope is often used to describe the measurement of the steepness, incline, gradient, or grade of a straight line
  - A higher slope value indicates a steeper incline
- The slope is defined as the <u>ratio</u> of the <u>altitude change</u> to the <u>horizontal distance</u> between any <u>two points</u> on the line
  - Using calculus, one can calculate the slope of the tangent to a curve at a point

$Δy$

$Δx$

HCI LAB

Slope Calculation

- Slope is defined as the change in the y coordinate divided by the corresponding change in the x coordinate, between two distinct points on the line

$$m = \frac{\Delta y}{\Delta x}$$

- Given two points (x_1, y_1) and (x_2, y_2), the change in x from one to the other is $x_2 - x_1$, while the change in y is $y_2 - y_1$

$$m = \frac{y_2 - y_1}{x_2 - x_1}$$

HCI LAB

Slope Special Cases

- The larger the absolute value of a slope, the steeper the line
  - A horizontal line has slope 0
    - Note that a vertical line's slope is undefined
  - A 45° rising line has a slope of +1
  - A 45° falling line has a slope of -1
- The angle **θ** a line makes with the positive **x** axis is closely related to the slope **m** via the tangent function:

$$m = \tan \theta \qquad \theta = \arctan m$$

HCI LAB

Slope Special Cases .

- Two lines are parallel if and only if
  - Their slopes are equal and they are not coincident or if
  - They both are vertical and therefore have undefined slopes
- Two lines are perpendicular if and only if
  - The product of their slopes is -1 or
  - One has a slope of 0 (a horizontal line) and the other has an undefined slope (a vertical line)

HCI LAB

Derivative

- By moving the two points closer together Δy and Δx decreases
  - The line more closely approximates a tangent line to the curve
  - The slope of the secant approaches that of the tangent
- If y is dependent on x, then it is sufficient to take the limit where only Δx approaches zero
- Therefore, the slope of the tangent is the limit of Δy/Δx as Δx approaches zero

$$m = \frac{\Delta y}{\Delta x}$$

HCI LAB

Differentiation and the Derivative

- **Differentiation** is a method to compute the rate at which a quantity, **y**, changes with respect to the change in another quantity, **x**, upon which it is **dependent**
- This **rate of change** is called the **derivative** of **y** with respect to **x**
- In more precise language, the dependency of y on x means that y is a function of x
- If x and y are real numbers, and if the graph of y is plotted against x, the **derivative** measures the **slope** of this graph at each point

HCI LAB

Differentiation and the Derivative .

- This functional relationship is often denoted y = f(x), where **f** denotes the function
- The simplest case is when y is a linear function of x, meaning that the graph of y against x is a straight line
- In this case, y = f(x) = m x + c, for real numbers m and c, and the slope m is given by

$$m = \frac{\text{change in } y}{\text{change in } x} = \frac{\Delta y}{\Delta x}$$

- where the symbol Δ is an abbreviation for 'change in'

HCI LAB

Differentiation and the Derivative ..

- It follows that Δy = m Δx
  - This gives an exact value for the slope of a straight line
- If the function f is not linear, then the change in y divided by the change in x varies
  - Differentiation is a method to find an exact value for this rate of change at any given value of x
- In Leibniz's notation, such an infinitesimal change in x is denoted by dx, and the derivative of y with respect to x is written:

$$\frac{dy}{dx}$$

HCI LAB

3D Line Parametric Equations

- In 3D a line is often described by parametric equations:

$$x = x_0 + at$$
$$y = y_0 + bt$$
$$z = z_0 + ct$$

- where:
  - x, y, and z are all functions of the independent variable t
  - x_0, y_0, and z_0 are the initial values of each respective variable
  - a, b, and c are related to the slope of the line, such that the vector (a, b, c) is a parallel to the line

HCI LAB

Ray

- In Euclidean geometry, a ray, or half-line, given two distinct points A (the origin) and B on the ray, is the set of points C on the line containing points A and B such that A is not strictly between C and B
- In geometry, a ray starts at one point, then goes on forever in one direction

HCI LAB

Example Class Tray.h

```
class TRay
{
    private:
        TVector _P; // Any point on the line
        TVector _V; // Direction of the line

    public:
        // Constructor
        TRay() {}

        // Line betwen two points OR point and a direction
        TRay(const TVector &point1, const TVector &point2);

        // Adjacent points on both lines
        bool adjacentPoints(const TRay &ray, TVector &point1, TVector &point2) const;

        // Distances
        double dist(const TRay &ray) const;
        double dist(const TVector &point) const;

        // More functions here
};
#endif
```
HCI LAB

Plane Definition

- A plane can be uniquely determined by any of the following (sets of) objects:
  - Three non-collinear points
    - i.e. not lying on the same line
  - A line and a point not on the line
  - Two lines with one point of intersection
  - Two parallel lines

HCI LAB

Plane Properties

- Two planes are either parallel or they intersect in a line
- A line is either parallel to a plane or intersects it at a single point or is contained in the plane
- Two lines normal (perpendicular) to the same plane must be parallel to each other
- Two planes normal to the same line must be parallel to each other

HCI LAB

Standard Plane Equation

- The standard equation of a plane in 3 space is:

$$Ax + By + Cz + D = 0$$

- The normal to the plane is the vector (A,B,C)

HCI LAB

Plane Definition with a Point and a Normal Vector

- In a 3D space, another important way of defining a plane is by specifying a point and a normal vector to the plane
- Let **p** be the point we wish to lie in the plane, and let **n** be a nonzero normal vector to the plane
- The desired plane is the set of all points **r** such that:

$$\vec{n} \cdot (\vec{r} - \vec{p}) = 0$$

HCI LAB

Plane Definition with a Point and a Normal Vector .

- If we write

$$\vec{n} = \begin{bmatrix} a \\ b \\ c \end{bmatrix} \qquad \mathbf{r} = (x, y, z)$$

- and d as the dot product

$$\vec{n} \cdot \mathbf{p} = -d$$

- then the plane Π is determined by the condition

$$ax + by + cz + d = 0$$

- where a, b, c and d are real numbers and a, b, and c are not all zero

HCI LAB

Define a Plane using three Points

- The plane passing through three points $p_1 = (x_1, y_1, z_1)$, $p_2 = (x_2, y_2, z_2)$ and $p_3 = (x_3, y_3, z_3)$ can be defined as the set of all points (x, y, z) that satisfy the following determinant equations:

$$\begin{vmatrix} x - x_1 & y - y_1 & z - z_1 \\ x_2 - x_1 & y_2 - y_1 & z_2 - z_1 \\ x_3 - x_1 & y_3 - y_1 & z_3 - z_1 \end{vmatrix} = \begin{vmatrix} x - x_1 & y - y_1 & z - z_1 \\ x - x_2 & y - y_2 & z - z_2 \\ x - x_3 & y - y_3 & z - z_3 \end{vmatrix} = 0$$

HCI LAB

Determinant

- A underline{determinant} is a function depending on n that associates a scalar, det(A), to every n×n square matrix A
- The determinant of a matrix A is also sometimes denoted by |A|

$$A = \begin{bmatrix} a & b & c \\ d & e & f \\ g & h & i \end{bmatrix} \qquad |A| = \begin{vmatrix} a & b & c \\ d & e & f \\ g & h & i \end{vmatrix}$$

HCI LAB

Dihedral Angle

- Given two intersecting planes described by

$$\Pi_1 : a_1 x + b_1 y + c_1 z + d_1 = 0$$

and

$$\Pi_2 : a_2 x + b_2 y + c_2 z + d_2 = 0$$

- the dihedral angle between them is defined to be the angle α between their normal directions

$$\cos \alpha = \hat{n}_1 \cdot \hat{n}_2 = \frac{a_1 a_2 + b_1 b_2 + c_1 c_2}{\sqrt{a_1^2 + b_1^2 + c_1^2} \sqrt{a_2^2 + b_2^2 + c_2^2}}.$$

HCI LAB

Minimum Distance between a Point and a Line

- Find the shortest distance from a point to a line or line segment
- The equation of a line defined through two points $P_1 (x_1, y_1)$ and $P_2 (x_2, y_2)$ is:

$$P = P_1 + u (P_2 - P_1)$$

HCI LAB

Minimum Distance between a Point and a Line .

- The point P_3 (x_3, y_3) is closest to the line at the tangent to the line which passes through P3, that is, the dot product of the tangent and line is equal to zero, thus:

$$(P_3 - P) \bullet (P_2 - P_1) = 0$$

- Substituting the equation of the line gives:

$$[P_3 - P_1 - u(P_2 - P_1)] \bullet (P_2 - P_1) = 0$$

HCI LAB

Minimum Distance between a Point and a Line ..

- Solving this gives the value of u

$$u = \frac{(x3 - x1)(x2 - x1) + (y3 - y1)(y2 - y1)}{\|p2 - p1\|^2}$$

- Substituting this into the equation of the line gives the point of intersection (x, y) of the tangent as

$$x = x_1 + u (x_2 - x_1)$$
$$y = y_1 + u (y_2 - y_1)$$

- The distance therefore between the point P3 and the line is the distance between (x, y) above and P3

HCI LAB

Minimum Distance between a Point and a Line …

- Notes
  - The only special testing for a software implementation is to ensure that P_1 and P_2 are not coincident (denominator in the equation for u is 0)
  - If the distance of the point to a line segment is required then it is only necessary to test that u lies between 0 and 1
  - The solution is similar in higher dimensions

HCI LAB

Minimum Distance between a Point and a Plane

- Let $P_a = (x_a, y_a, z_a)$ be the point in question
- A plane can be defined by its normal n = (A, B, C) and any point on the plane $P_b = (x_b, y_b, z_b)$

- Any point P = (x, y, z) lies on the plane if it satisfies the following

$$A x + B y + C z + D = 0$$

HCI LAB

Minimum Distance between a Point and a Plane .

- Consider the projection of the line $(P_a - P_b)$ onto the normal of the plane n, that is just $||P_a - P_b|| \cos\theta$
  - Where θ is the angle between $(P_a - P_b)$ and the normal n
- This projection is the minimum distance (D) of P_a to the plane and can be written in terms of the dot product:

$$D = (P_a - P_b) \bullet n / ||n||$$

- That is: $D = (A (x_a - x_b) + B (y_a - y_b) + C (z_a - z_b))$ / sqrt($A^2 + B^2 + C^2$)

HCI LAB

Minimum Distance between a Point and a Plane ..

- Since point (x_b, y_b, z_b) is a point on the plane

$$Ax_b + By_b + Cz_b + D = 0$$

- Substituting gives:

$$(Ax_a + By_a + Cz_a + D) / sqrt(A^2 + B^2 + C^2)$$

HCI LAB

Point inside a Triangle

- Consider a triangle T defined by 3 points $p_1(x_1, y_1)$, $p_2(x_2, y_2)$, $p_3(x_3, y_3)$ and a single point $p(x, y)$
- Four solutions:
  - Barycentric solution
  - Parametric solution
  - Dot product solution
  - Cross product solution

HCI LAB

Barycentric Solution

- Barycentric coordinate allows to express new p coordinates as a linear combination of p_1, p_2, p_3
- More precisely, it defines 3 scalars a, b, c such that :
  - $x = a * x_1 + b * x_2 + c * x_3$
  - $y = a * y_1 + b * y_2 + c * y_3$
  - $a + b + c = 1$

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Barycentric Solution .

- The way to compute a, b, c is not difficult :
  - $a = ((y_2 - y_3)*(x - x_3) + (x_3 - x_2)*(y - y_3)) / ((y_2 - y_3)*(x_1 - x_3) + (x_3 - x_2)*(y_1 - y_3))$
  - $b = ((y_3 - y_1)*(x - x_3) + (x_1 - x_3)*(y - y_3)) / ((y_2 - y_3)*(x_1 - x_3) + (x_3 - x_2)*(y_1 - y_3))$
  - $c = 1 - a - b$
- Then p lies in T if and only if:
  - $0 <= a <= 1$ and $0 <= b <= 1$ and $0 <= c <= 1$

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Barycentric Code Sample

```
function pointInTriangle(x1, y1, x2, y2, x3, y3, x, y: Number):
    Boolean
{
    var denominator:Number = ((y2 - y3)*(x1 - x3) + (x3 - x2)*(y1 - y3));
    var a:Number = ((y2 - y3)*(x - x3) + (x3 - x2)*(y - y3)) / denominator;
    var b:Number = ((y3 - y1)*(x - x3) + (x1 - x3)*(y - y3)) / denominator;
    var c:Number = 1 - a - b;

    return 0 <= a && a <= 1 && 0 <= b && b <= 1 && 0 <= c && c
    <= 1;
}
```

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Parametric Solution

- Consider the parametric expressions of the 2 edges $[p_1, p_2]$ and $[p_1, p_3]$ in T :
  - $x(t1) = t1*(x_2 - x_1)$
  - $y(t1) = t1*(y_2 - y_1)$
  - $x(t2) = t2*(x_3 - x_1)$
  - $y(t2) = t2*(y_3 - y_1)$
- Then express p(x, y) as a linear combination of them:
  - $x = x_1 + x(t1) + x(t2)$
  - $y = y_1 + y(t1) + y(t2)$

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Parametric Solution .

- Solving the system:
  - $t1 = (x*(y_3 - y_1) + y*(x_1 - x_3) - x_1*y_3 + y_1*x_3) / (x_1*(y_2 - y_3) + y_1*(x_3 - x_2) + x_2*y_3 - y_2*x_3)$
  - $t2 = (x*(y_2 - y_1) + y*(x_1 - x_2) - x_1*y_2 + y_1*x_2) / -(x_1*(y_2 - y_3) + y_1*(x_3 - x_2) + x_2*y_3 - y_2*x_3)$
- Then p lies in T if and only if:
  - $0 <= t1 <= 1$ and $0 <= t2 <= 1$ and $t1 + t2 <= 1$

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Parametric Code Sample

```
function pointInTriangle(x1, y1, x2, y2, x3, y3, x, y: Number):
    Boolean
{
    var denominator:Number = (x1*(y2 - y3) + y1*(x3 - x2) + x2*y3
      - y2*x3);
    var t1:Number = (x*(y3 - y1) + y*(x1 - x3) - x1*y3 + y1*x3) /
      denominator;
    var t2:Number = (x*(y2 - y1) + y*(x1 - x2) - x1*y2 + y1*x2) / -
      denominator;
    var s:Number = t1 + t2;

    return 0 <= t1 && t1 <= 1 && 0 <= t2 && t2 <= 1 && s <= 1;
}
```

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Dot Product Solution

- Assume that p_1, p_2, p_3 are ordered in counterclockwise and check if p lies at left of the 3 oriented edges
  – $[p_1, p_2], [p_2, p_3], [p_3, p_1]$
- First consider the 3 vectors v_1, v_2 and v_3 that are left-orthogonal to $[p_1, p_2], [p_2, p_3]$ and $[p_3, p_1]$:
  – $v_1 = <y_2 - y_1, -x_2 + x_1>$
  – $v_2 = <y_3 - y_2, -x_3 + x_2>$
  – $v_3 = <y_1 - y_3, -x_1 + x_3>$
- Then we get the 3 following vectors :
  – $v_1' = <x - x_1, y - y_1>$
  – $v_2' = <x - x_2, y - y_2>$
  – $v_3' = <x - x_3, y - y_3>$

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Dot Product Solution .

- Compute the 3 dot products:
  – dot1 = $v_1 . v_1' = (y_2 - y_1)*(x - x_1) + (-x_2 + x_1)*(y - y_1)$
  – dot2 = $v_1 . v_2' = (y_3 - y_2)*(x - x_2) + (-x_3 + x_2)*(y - y_2)$
  – dot3 = $v_3 . v_3' = (y_1 - y_3)*(x - x_3) + (-x_1 + x_3)*(y - y_3)$
- Check if p lies in T if and only if
  – 0 <= dot1 and 0 <= dot2 and 0 <= dot3

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Dot Product Sample Code

```
function side(x1, y1, x2, y2, x, y:Number):Number
{
    return (y2 - y1)*(x - x1) + (-x2 + x1)*(y - y1);
}


function pointInTriangle(x1, y1, x2, y2, x3, y3, x, y:
    Number): Boolean
{
    var checkSide1:Boolean = side(x1, y1, x2, y2, x, y) >= 0;
    var checkSide2:Boolean = side(x2, y2, x3, y3, x, y) >= 0;
    var checkSide3:Boolean = side(x3, y3, x1, y1, x, y) >= 0;
    return checkSide1 && checkSide2 && checkSide3;
}
```

http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html
HCI LAB

Cross Product Solution

- Calculate:
  – c1 = p_1 x p
  – c2 = p_2 x p
  – c3 = p_3 x p
- P is inside triangle if:
  – Clockwise order if
    - c1> 0 && c2> 0 && c3 > 0
  – Counterclockwise if
    - c1< 0 && c2< 0 && c3 < 0
  – No information if
    - (c1> 0 && c2> 0 && c3 > 0) || (c1< 0 && c2< 0 && c3 < 0)

http://www.sunshine2k.de/coding/java/PointInTriangle/PointInTriangle.html
HCI LAB

Conic Sections

- A conic section is a curve obtained as the intersection of a cone (more precisely, a right circular conical surface) with a plane

HCI LAB

Circle

- The *circumference* of a circle means the length of the circle
- The interior of the circle is called a *disk*
- An *arc* is any continuous portion of a circle
- A *diameter* is a straight line through the center and terminating in both directions on the circumference

HCI LAB

Equation of a Circle

- In an x-y coordinate system, the circle with centre (a, b) and radius r is the set of all points (x, y) such that:

$$(x - a)^2 + (y - b)^2 = r^2$$

- The equation of the circle follows from the Pythagorean theorem applied to any point on the circle

HCI LAB

Circle at Origin

- If the circle is centred at the origin (0, 0), then the above formula can be simplified:

$$x^2 + y^2 = r^2$$

- and its tangent will be:

$$xx_1 + yy_1 = r^2$$

- where x_1, y_1 are the coordinates of the common point

HCI LAB

Tangent and Secant Lines

- A line is tangent to a curve, at some point, if both line and curve pass through the point with the same direction
  - This is called the tangent line
  - Tangent line is the best straight-line approximation to the curve at that point
- The slope of a tangent line can be approximated by a secant line
  - It is a mistake to think of tangents as lines which intersect a curve at only one single point

HCI LAB

Circle Parametric Equations

- When expressed in parametric equations (x, y) can be written using the trigonometric functions sine and cosine as:

  x = a + r cost

  y = b + r sint

- where t is a parametric variable
  - Understood as the angle the ray to (x, y) makes with the x-axis

HCI LAB

Definition of π

- π symbolizes the ratio
  - The relationship with respect to relative size of the circumference of circle to its diameter, whatever that relationship might be
  - So when we say that π ≈ 3.14, we mean that the circumference of circle is a little more than three times longer than the diameter:

  C / D = π ≈ 3.14

  - π indicates the ratio of a curved line to a straight

HCI LAB

Circumference of a Circle

- Since: C / D = π
- Can use that as a formula for calculating the circumference of a circle:

$$C = \pi D$$

- Or, since D = 2r

$$C = \pi \cdot 2r = 2\pi r$$

HCl LAB

Calculation of Area Enclosed

- The area enclosed by a circle is the radius squared, multiplied by π

$$A = r^2 \cdot \pi$$

Area = r^2

Circle Area = $\pi \times r^2$

HCl LAB

Calculation of Area Enclosed .

- Using a square with side lengths equal to the diameter of the circle, then dividing the square into four squares with side lengths equal to the radius of the circle, take the area of the smaller square and multiply by π

$$d = 2r = 2 \cdot \sqrt{\frac{A}{\pi}} \approx 1.1284 \cdot \sqrt{A}$$

– approximately 79% of the circumscribing square

HCl LAB

Unit Circle

- A unit circle is a circle with a unit radius
  – This is a circle whose radius is 1
- Often, the unit circle is the circle of radius 1 centered at the origin (0, 0) in the Cartesian coordinate system in the Euclidean plane
  – If (x, y) is a point on the unit circle in the first quadrant, then x and y are the lengths of the legs of a right triangle whose hypotenuse has length 1, then:

$(\cos t, \sin t)$

$$x^2 + y^2 = 1$$

HCl LAB

Circle Properties

- The circle is the shape with the highest area for a given length of perimeter
- The circle is a highly symmetric shape
  – Every line through the centre forms a line of reflection symmetry and it has rotational symmetry around the centre for every angle
- All circles are similar:
  – A circle's circumference and radius are proportional
  – The area enclosed and the square of its radius are proportional
  – The constants of proportionality are 2π and π, respectively

HCl LAB

Calculate x, y of Segment

z

x

d = 2sqrt(r²-x²)

HCl LAB

Calculate x, y of Segment .

$d = 2sqrt(r^2-x^2) \rightarrow z = sqrt(r^2 - x^2) \rightarrow$
$z = sqrt(r^2 - r^2/(1 + tan\theta^2) \rightarrow$
$z = r \ sqrt(1 - 1 / (1 + tan\theta^2)$

$z = sqrt(r^2-x^2) \rightarrow z^2 = r^2-x^2$

But $tan\theta = z/x$, so:

$x^2 tan\theta^2 = r^2-x^2 \rightarrow x^2(1+ tan\theta^2) = r^2 \rightarrow$
$x = r/sqrt(1 + tan\theta^2)$

HCI LAB

Ground Implementation in C++

- TGround Class
  - Variables
    - Define 37 points in the surface of the ground
    - Define the normal of the ground
  - Functions
    - Ground Constructor
    - Draw Ground

HCI LAB

TGround Class

```
class TGround
{
    public:
        TVector _points[37];  // points in the surface of the
ground
        TVector _normal;              // normal of the ground

    public:
        // Default constructor
        TGround();

        // Function that draws the ground
        void DrawGround();
};
```

HCI LAB

Constructor

```
for(i=0; i<=36; i++)
{
    // Transform degrees in rads
    rad_angle=(pi*angle)/180.0;

    // Calculate the x and z co-ordinates of a circle ground
    x = radius/(sqrt(1.0 + tan(rad_angle)*tan(rad_angle)));
    z = radius*(sqrt(1.0 - (1.0/(1.0 +  tan(rad_angle)*tan(rad_angle)))));
    angle += 10;

    // Check the co-ordinates in all the quadrants of the circle ground
    if ((i>=0) && (i<10))              // First quadrant
    {
            if (i==9) {  _points[i] = TVector(0.0, 0.0, 1.0);  }
                    _points[i] = TVector(x, y, z);
    }
    if ((i>=10) && (i<19))                    // Second quadrant
    {
            _points[i] = TVector(-x, y, z);
    }
    if ((i>=19) && (i<28))                    // Third quadrant
    {
            if (i==27) {  _points[i] = TVector(0.0, 0.0, -1.0); }
            _points[i] = TVector(-x, y, -z);
    }
    if ((i>=27) && (i<36))                    // Fourth quadrant
    {
            _points[i] = TVector(x, y, -z);
    }
}
// Construct the vector for the normal of the ground
_normal = TVector(0.0, 1.0, 0.0);
```

HCI LAB

Draw Ground Function

```
void TGround::DrawGround()
{
    int i=0.0;

    glPushMatrix();
    glPushAttrib(GL_ENABLE_BIT);
    glCallList(50);

    glBegin(GL_POLYGON);
    for(i=0; i<=36; i++)
    {
        glNormal3f(0.0, 1.0, 0.0);
        glVertex3f(_points[i].X(), _points[i].Y(), _points[i].Z());
    }
    glEnd();

    glPopAttrib();
    glPopMatrix();
}
```

HCI LAB

Ellipse

- An ellipse is a curve on a plane surrounding two focal points such that the sum of the distances to the two focal points is constant for every point on the curve

$$\frac{x^2}{a^2} + \frac{y^2}{b^2} = 1$$

- You can think of an ellipse as an oval

HCI LAB

Parabola

- The standard form of a parabola's equation is generally expressed:
  $$y = ax^2 + bx + c$$
  – $y = ax^2 + bx + c$
- The role of 'a'
  – If $a > 0$, the parabola opens upwards
  – If $a < 0$, it opens downwards
- The axis of symmetry
  – The axis of symmetry is the line $x = -b/2a$

HCI LAB

Vertex Form of Parabola

- The vertex form of a parabola's equation is generally expressed as:
  – $y = a(x-h)^2 + k$ where (h,k) is the vertex
- If a is + then the parabola opens upwards like a regular "U"
- If a is - then the graph opens downwards like an upside down "U"
- If $|a| < 1$, the graph of the parabola widens
- If $|a| > 1$, the graph of the graph becomes narrower
  – The effect is the opposite of $|a| < 1$

HCI LAB

Hyperbola

- The equation of the hyperbola can be written as:
  $$\frac{x^2}{a^2} - \frac{y^2}{b^2} = 1$$
- If c is the distance from the center to either focus, then:
  $$a^2 + b^2 = c^2$$

HCI LAB

Parametric surfaces

- A torus with major radius R and minor radius r may be defined parametrically as
  $x = \cos(t)(R + r\cos(u))$
  $y = \sin(t)(R + r\cos(u))$
  $z = r\sin(u)$
- where the two parameters t and u both vary between 0 and 2π

HCI LAB

Equation of a Sphere

- Pythagoras theorem generalises to 3D giving:
  – $a^2 + b^2 + c^2 = d^2$
- Based on that we can easily prove that the general equation of a sphere is:
  – $(x - x_c)^2 + (y - y_c)^2 + (z - z_c)^2 = r^2$
- and at origin:
  – $x^2 + y^2 + z^2 = r^2$

HCI LAB

Ray-Sphere Intersection

Ray: $P = P_0 + tV$
Sphere: $(x - c_x)^2 + (y - c_y)^2 + (z - c_z)^2 = r^2$ or $|P - C|^2 - r^2 = 0$

Substituting for P, we get: $|P_0 + tV - C|^2 - r^2 = 0$

Solve quadratic equation: $at^2 + bt + c = 0$

where:
   $a = |V|^2 = 1$
   $b = 2 V \cdot (P_0 - C)$
   $c = |P_0 - C|^2 - r^2$

$P = P_0 + tV$

HCI LAB

Advanced Methods of Rotation

- Different advanced methods exist including:
  - Euler angles
  - Quaternions

Euler Angles

- In many fields Euler angles are used to represent rotations
- Any rotation can be broken down into a series of three rotations about the major axes

Euler Angles .

- We can simulate any arbitrary rotation with one rotation about the x-axis, one about the y-axis, and then one about the z-axis
  - i.e. consider an airplane pointing along the x-axis with the z-axis pointing up

Roll, Pitch, Yaw

- Can represent any pose as a vector (roll, pitch, yaw)
  - The "roll" about the x-axis along the plane
  - The "pitch" about the y-axis which extends along the wings of the plane
  - The "yaw" or "heading" about the z-axis

Disadvantages

- No universal standard for Euler rotations
  - Different fields use different sequences
    - i.e. some use z-y-z as opposed to the x-y-z system
- Although any rotation can be represented by either a set of Euler angles or a matrix
  - Computing the required angles is expensive and can introduce errors
- Interpolation does not work well!

Standard Rotations

$$\begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix}$$

$$\begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix}$$

$$\begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix}$$

Angles to Axis

- Can combine the separate axis rotations into one matrix by multiplying standard rotational matrices together
  - Multiplication of matrices is not commutative
    - Different order of matrix multiplication results in a different outcome
- 6 different combinations are possible;
  - $R_xR_yR_z$, $R_xR_zR_y$, $R_yR_xR_z$, $R_yR_zR_x$, $R_zR_xR_y$ and $R_zR_yR_x$

HCI LAB

$R_xR_yR_z$ & $R_xR_zR_y$ Rotations

$$R_X R_Y R_Z$$
$$= \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix} \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix} \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix}$$
$$= \begin{pmatrix} \cos B & 0 & \sin B \\ \sin A \sin B & \cos A & -\sin A \cos B \\ -\cos A \sin B & \sin A & \cos A \cos B \end{pmatrix} \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix}$$
$$= \begin{pmatrix} \cos B \cos C & -\cos B \sin C & \sin B \\ \sin A \sin B \cos C + \cos A \sin C & -\sin A \sin B \sin C + \cos A \cos C & -\sin A \cos B \\ -\cos A \sin B \cos C + \sin A \sin C & \cos A \sin B \sin C + \sin A \cos C & \cos A \cos B \end{pmatrix}$$

$$R_X R_Z R_Y$$
$$= \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix} \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix}$$
$$= \begin{pmatrix} \cos C & -\sin C & 0 \\ \cos A \sin C & \cos A \cos C & -\sin A \\ \sin A \sin C & \sin A \cos C & \cos A \end{pmatrix} \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix}$$
$$= \begin{pmatrix} \cos C \cos B & -\sin C & \cos C \sin B \\ \cos A \sin C \cos B + \sin A \sin B & \cos A \cos C & \cos A \sin C \sin B - \sin A \cos B \\ \sin A \sin C \cos B - \cos A \sin B & \sin A \cos C & \sin A \sin C \sin B + \cos A \cos B \end{pmatrix}$$

HCI LAB

$R_yR_xR_z$ & $R_yR_zR_x$ Rotations

$$R_Y R_X R_Z$$
$$= \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix} \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix}$$
$$= \begin{pmatrix} \cos B & \sin B \sin A & \sin B \cos A \\ 0 & \cos A & -\sin A \\ -\sin B & \cos B \sin A & \cos B \cos A \end{pmatrix} \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix}$$
$$= \begin{pmatrix} \cos B \cos C + \sin B \sin A \sin C & -\cos B \sin C + \sin B \sin A \cos C & \sin B \cos A \\ \cos A \sin C & \cos A \cos C & -\sin A \\ -\sin B \cos C + \cos B \sin A \sin C & \sin B \sin C + \cos B \sin A \cos C & \cos B \cos A \end{pmatrix}$$

$$R_Y R_Z R_X$$
$$= \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix} \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix}$$
$$= \begin{pmatrix} \cos B \cos C & -\cos B \sin C & \sin B \\ \sin C & \cos C & 0 \\ -\sin B \cos C & \sin B \sin C & \cos B \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix}$$
$$= \begin{pmatrix} \cos B \cos C & -\cos B \sin C \cos A + \sin B \sin A & \cos B \sin C \sin A + \sin B \cos A \\ \sin C & \cos C \cos A & -\cos C \sin A \\ -\sin B \cos C & \sin B \sin C \cos A + \cos B \sin A & -\sin B \sin C \sin A + \cos B \cos A \end{pmatrix}$$

HCI LAB

$R_zR_xR_y$ & $R_zR_yR_x$ Rotations

$$R_Z R_X R_Y$$
$$= \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix} \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix}$$
$$= \begin{pmatrix} \cos C & -\sin C \cos A & \sin C \sin A \\ \sin C & \cos C \cos A & -\cos C \sin A \\ 0 & \sin A & \cos A \end{pmatrix} \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix}$$
$$= \begin{pmatrix} \cos C \cos B - \sin C \sin A \sin B & -\sin C \cos A & \cos C \sin B + \sin C \sin A \cos B \\ \sin C \cos B + \cos C \sin A \sin B & \cos C \cos A & \sin C \sin B - \cos C \sin A \cos B \\ -\cos A \sin B & \sin A & \cos A \cos B \end{pmatrix}$$

$$R_Z R_Y R_X$$
$$= \begin{pmatrix} \cos C & -\sin C & 0 \\ \sin C & \cos C & 0 \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} \cos B & 0 & \sin B \\ 0 & 1 & 0 \\ -\sin B & 0 & \cos B \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix}$$
$$= \begin{pmatrix} \cos C \cos B & -\sin C & \cos C \sin B \\ \sin C \cos B & \cos C & \sin C \sin B \\ -\sin B & 0 & \cos B \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos A & -\sin A \\ 0 & \sin A & \cos A \end{pmatrix}$$
$$= \begin{pmatrix} \cos C \cos B & -\sin C \cos A + \cos C \sin B \sin A & \sin C \sin A + \cos C \sin B \cos A \\ \sin C \cos B & \cos C \cos A + \sin C \sin B \sin A & -\cos C \sin A + \sin C \sin B \cos A \\ -\sin B & \cos B \sin A & \cos B \cos A \end{pmatrix}$$

HCI LAB

Code Example

```
void anglesToAxes(const Vector3 angles, Vector3& left, Vector3& up, Vector3& forward)
{
    const float DEG2RAD = 3.141593f / 180;
    float sx, sy, sz, cx, cy, cz, theta;

    // rotation angle about X-axis (pitch)
    theta = angles.x * DEG2RAD;
    sx = sinf(theta);
    cx = cosf(theta);

    // rotation angle about Y-axis (yaw)
    theta = angles.y * DEG2RAD;
    sy = sinf(theta);
    cy = cosf(theta);

    // rotation angle about Z-axis (roll)
    theta = angles.z * DEG2RAD;
    sz = sinf(theta);
    cz = cosf(theta);
}
```

HCI LAB

Code Example .

```
left.x = cy*cz;
left.y = sx*sy*cz + cx*sz;           determine left axis
left.z = -cx*sy*cz + sx*sz;

up.x = -cy*sz;
up.y = -sx*sy*sz + cx*cz;            determine up axis
up.z = cx*sy*sz + sx*cz;

forward.x = sy;
forward.y = -sx*cy;                  determine forward axis
forward.z = cx*cy;
```

HCI LAB

Rotation About Arbitrary Axis

- In addition to the set of three Euler angles and the rotation matrix, a rotation can also be represented by a vector specifying the rotation axis and the angle of rotation around this axis
- The problem of rotation about an arbitrary axis in three dimensions arises in many fields including computer graphics and computer games

HCI LAB

3x3 Matrix Representing Axis

- We can express the 3×3 rotation matrix in terms of a 3×3 matrix representing the axis:
  - [R] = [I] + s*[~axis] + t*[~axis]^2

- or equivalently:
  - [R] = c*[I] + s*[~axis] + t*([~axis]^2 + [I])

HCI LAB

Matrix Expansion

$$[R] = \begin{bmatrix} t*x*x + c & t*x*y - z*s & t*x*z + y*s \\ t*x*y + z*s & t*y*y + c & t*y*z - x*s \\ t*x*z - y*s & t*y*z + x*s & t*z*z + c \end{bmatrix}$$

- where:
  - c = cos(angle)
  - s = sin(angle)
  - t = 1 - c
  - x = normalised axis x coordinate
  - y = normalised axis y coordinate
  - z = normalised axis z coordinate

HCI LAB

Code Example

```
public void matrixFromAxisAngle(AxisAngle4d a1)
{
    double c = Math.cos(a1.angle);
    double s = Math.sin(a1.angle);
    double t = 1.0 - c;

    m00 = c + a1.x*a1.x*t;
    m11 = c + a1.y*a1.y*t;
    m22 = c + a1.z*a1.z*t;

    double tmp1 = a1.x*a1.y*t;
    double tmp2 = a1.z*s;

    m10 = tmp1 + tmp2;
    m01 = tmp1 - tmp2;
    tmp1 = a1.x*a1.z*t;
    tmp2 = a1.y*s;
    m20 = tmp1 - tmp2;
    m02 = tmp1 + tmp2;    tmp1 = a1.y*a1.z*t;
    tmp2 = a1.x*s;
    m21 = tmp1 + tmp2;
    m12 = tmp1 - tmp2;
}
```

HCI LAB

Quaternions

- Complex numbers were discovered in 1800's and had the characteristic property to be defined in terms of i, where i is the square root of –1
- In 1843, sir William Rowan Hamilton discovered a number called the quaternion, which has a very similar form to complex numbers

HCI LAB

Quaternion Definition

- A quaternion is based on three different numbers that are all square roots of –1 and are labeled i, j and k, where:

$$q = (z_1, z_2, z_3, s) = (\mathbf{z}, s)$$
$$q = iz_1 + jz_2 + kz_3 + s$$

$$i^2 = j^2 = k^2 = -1 \qquad \begin{matrix} ij = k & ji = -k \\ jk = i & kj = -i \\ ki = j & ik = -j \end{matrix}$$

HCI LAB

Quaternion Properties

Multiplication natural consequence of defn.

$$q \cdot p = \left(\mathbf{z}_q s_p + \mathbf{z}_p s_q + \mathbf{z}_p \times \mathbf{z}_q \ , \ s_p s_q - \mathbf{z}_p \cdot \mathbf{z}_q\right)$$

Conjugate

$$q^* = (-\mathbf{z}, s)$$

Magnitude

$$||q||^2 = \mathbf{z} \cdot \mathbf{z} + s^2 = q \cdot q^*$$

HCI LAB

Quaternion Rotations

Vectors as quaternions

$$v = (\mathbf{v}, 0)$$

Rotations as quaternions

$$r = (\hat{\mathbf{r}} \sin\frac{\theta}{2}, \cos\frac{\theta}{2})$$

Rotating a vector

$$x' = r \cdot x \cdot r^*$$

Composing rotations

$$r = r_1 \cdot r_2 \quad \longleftarrow \quad \text{Compare to Exp. Map}$$

HCI LAB

Quaternion Representation

- Defined like complex numbers but with 4 coordinates
  - q[w, (x, y, z)] also written q[w, v] where v = (x, y, z)
  - q = w + xi + yj + zk
    - Here, *w* is real part, and *(x,y,z)* are imaginary parts
    - Think of *w* as angle in an angle-axis representation
    - Think of *(x, y, z)* as axis in an axis-angle representation
- Based on three different roots of -1:
  - $i^2 = j^2 = k^2 = -1$

HCI LAB

Quaternion Representation .

- For a right-hand rotation of θ **radians** about unit vector *v*, quaternion is:

  $$q = (\cos(\theta/2); \mathbf{v}\sin(\theta/2))$$

  - Note how the 3 imaginary coordinates are noted as a vector
  - Only **unit quaternions** represent rotations
    - Such a quaternion describes a point on the 4D unit hyper-sphere
  - Important note: q and –q represent the **exact same** orientation

HCI LAB

Quaternion Toolbox

- Addition
  - $q^1 + q^2 = [w^1 + w^2, v^1 + v^2]$
- Multiplication
  - $q^1q^2 = [w^1w^2 - v^1.v^2, v^1 \times v^2 + w^1v^2 + w^2v^1]$ (note: $q^1q^2 \mathrel{!=} q^2q^1$)
- Magnitude
  - $|q| = sqrt(w^2 + x^2 + y^2 + z^2)$
- Normalisation
  - $N(q) = q / |q|$
- Conjugate
  - $q^* = [w, -v]$
- Inverse
  - $q^{-1} = q^* / |q|^2$
- Unit quternion
  - q is unit if $|q| = 1$ and $q^{-1} = q^*$
- Identity
  - $q^{identity} = [1,(0,0,0)]$ for multiplication, $q^{identity} = [0,(0,0,0)]$ for addition

HCI LAB

Transforming a Point or Vector

- To transform a vector P by the rotation specified by the quaternion q, there are two options:
  - Multiply conj(q) by (0, Px, Py, Pz)
    - See next slide
  - Convert q to matrix and use matrix transformation

HCI LAB

First Method

- Rotate vector P angle θ around unit axis R:
  - Form the quaternion representing the vector P
    - q1 = (0,Px,Py,Pz)
  - Form the rotation quaternion from the axis R and angle θ
    - q2 = (cos(θ/2),Rx sin(θ/2),Ry sin(θ/2),Rz sin(θ/2))
  - The rotated vector is given by v entry of the quaternion:
    - q3 = q2 q1 q2*
      - q2 must be of unit magnitude for this to work properly

HCI LAB

Quaternion and Axis-Angle

- From axis-angle to quaternion:
  - q = (cos(θ/2); v sin(θ/2))
  - where:
    - v is the axis
    - θ is the angle
- From quaternion to axis-angle:
  - Axis v = (x, y, z) / sqrt($x^2 + y^2 + z^2$)
  - Angle θ = acos(w) * 2

HCI LAB

Quaternion to Matrix

- From quaternion to a 3x3 rotation matrix:

$$\begin{vmatrix} 1-2y^2-2z^2 & 2yz+2wx & 2xz-2wy \\ 2xy-2wz & 1-2x^2-2z^2 & 2yz-2wx \\ 2xz+2wy & 2yz-2wx & 1-2x^2-2y^2 \end{vmatrix}$$

HCI LAB

Euler Angles to Quaternion

- From Euler angles (pitch, yaw, roll)
  - Create three quaternions
  - One for each of pitch, roll, yaw
  - Then multiply them together
- Here, P = pitch/2, Y = yaw/2, R = roll/2
  - w = cos(R)*cos(P)*cos(Y) + sin(R)*sin(P)*sin(Y)
  - x = sin(R)*cos(P)*cos(Y) − cos(R)*sin(P)*sin(Y)
  - y = cos(R)*sin(P)*cos(Y) + sin(R)*cos(P)*sin(Y)
  - z = cos(R)*cos(P)*sin(Y) − sin(R)*sin(P)*cos(Y)

HCI LAB

Quaternion Code Example

- Three functions:
  - Convert an axis and angle rotation to a quaternion
  - Convert a quaternion to a rotation matrix
  - Rotate the quaternion

HCI LAB

Convert an axis and angle rotation to a quaternion

```
void Tquaternion::CreateFromAxisAngle(float X,
    float Y, float Z, float degree)
{
    float angle = float((degree / 180.0f) * PI);
    float result = (float)sin( angle / 2.0f );
    w = (float)cos( angle / 2.0f );
    x = float(X * result);
    y = float(Y * result);
    z = float(Z * result);
}
```

HCI LAB

Convert a quaternion to a rotation matrix

```
void Tquaternion::CreateMatrix(float *pMatrix)
{
    pMatrix[ 0] = 1.0f - 2.0f * ( y * y + z * z );
    pMatrix[ 1] = 2.0f * (x * y + z * w);
    pMatrix[ 2] = 2.0f * (x * z - y * w);
    pMatrix[ 3] = 0.0f;
    pMatrix[ 4] = 2.0f * ( x * y - z * w );
    pMatrix[ 5] = 1.0f - 2.0f * ( x * x + z * z );
    pMatrix[ 6] = 2.0f * (z * y + x * w );
    pMatrix[ 7] = 0.0f;
    pMatrix[ 8] = 2.0f * ( x * z + y * w );
    pMatrix[ 9] = 2.0f * ( y * z - x * w );
    pMatrix[10] = 1.0f - 2.0f * ( x * x + y * y );
    pMatrix[11] = 0.0f;
    pMatrix[12] = 0;
    pMatrix[13] = 0;
    pMatrix[14] = 0;
    pMatrix[15] = 1.0f;
}
```

HCI LAB

Rotate the Quaternion

```
void Tquaternion::quaternionRotation(double x, double y, double z)
{
    float matrixX[16], matrixY[16], matrixZ[16];
    static float rotation = 0;

    Tquaternion qRotationX;
    Tquaternion qRotationY;
    Tquaternion qRotationZ;
    qRotationX.CreateFromAxisAngle(1, 0, 0, x);
    qRotationY.CreateFromAxisAngle(0, 1, 0, y);
    qRotationZ.CreateFromAxisAngle(0, 0, 1, z);

    qRotationX.CreateMatrix(matrixX);
    qRotationY.CreateMatrix(matrixY);
    qRotationZ.CreateMatrix(matrixZ);

    glMultMatrixf(matrixX);
    glMultMatrixf(matrixY);
    glMultMatrixf(matrixZ);
}
```

HCI LAB

Quaternion Interpolation

- One of the most important reasons for using quaternions is that they are very good at representing rotations in space
- Quaternions overcome the issues that plague other methods of rotating points in 3D space such as Gimbal lock
 - An issue when you represent your rotation with Euler angles

HCI LAB

Quaternion Interpolation Methods

- Using quaternions can define several methods that represents a rotational interpolation in 3D space:
  - SLERP
    - Used to smoothly interpolate a point between two orientations
  - SQAD (extension of SLERP)
    - Used to interpolate through a sequence of orientations that define a path

HCI LAB

Examples

HCI LAB

SLERP

- SLERP provides a method to smoothly interpolate a point about two orientations
  - SLERP stands for Spherical Linear Interpolation
- Represent the first orientation as q_1 and the second orientation as q_2
- The point that is interpolated will be represented by P and the interpolated point will be represented by P$'$
- The interpolation parameter t will interpolate P from q_1 when t=0 to q_2 when t=1

HCI LAB

SLERP Interpolation

- The standard linear interpolation formula is:
$$p' = p_1 + t(p_2 - p_1)$$
- The general steps to apply this equation are:
  - Compute the difference between p_1 and p_2
  - Take the fractional part of that difference
  - Adjust the original value by the fractional difference between the two points
- Can use the same principle to interpolate between two quaternion orientations

HCI LAB

SQAD

- SQUAD (Spherical and Quadrangle) can be used to smoothly interpolate over a path of rotations
  - Just as a SLERP can be used to compute an interpolation between two quaternions
- If we have the sequence of quaternions:
$$q_1, q_2, q_3, \cdots, q_{n-2}, q_{n-1}, q_n$$

HCI LAB

SQAD Representation

- And we also define the "helper" quaternion (s_i) which we can consider an intermediate control point:

$$s_i = \exp\left(-\frac{\log\left(q_{i+1} q_i^{-1}\right) + \log\left(q_{i-1} q_i^{-1}\right)}{4}\right) q_i$$

HCI LAB

SQAD Orientation

- Then the orientation along the sub-curve defined by:
$$q_{i-1}, q_i, q_{i+1}, q_{i+2}$$
- at time t is given by:

$$\mathrm{squad}(q_i, q_{i+1}, s_i, s_{i+1}, t) = \mathrm{slerp}(\mathrm{slerp}(q_i, q_{i+1}, t), \mathrm{slerp}(s_i, s_{i+1}, t), 2t(1-t))$$

HCI LAB

Quaternion Advantages

- Quaternion interpolation using SLERP and SQUAD provide a way to interpolate smoothly between orientations in space
- Rotation concatenation using quaternions is faster than combining rotations expressed in matrix form
- Converting quaternions to matrices is slightly faster than for Euler angles
- Quaternions only require 4 numbers
  - 3 if they are normalized
  - The Real part can be computed at run-time
    - To represent a rotation where a matrix requires at least 9 values

HCI LAB

Quaternion Disadvantages

- Very hard to understand
- Can become invalid because of floating-point round-off error
  - This can be resolved by re-normalizing the quaternion

HCI LAB

References

- http://www.songho.ca/opengl/gl_anglestoaxes.html
- http://inside.mines.edu/~gmurray/ArbitraryAxisRotation/
- http://www.euclideanspace.com/maths/geometry/rotations/conversions/angleToMatrix/
- http://en.wikipedia.org/wiki/Euler_angles
- http://en.wikipedia.org/wiki/Line_(mathematics)
- http://en.wikipedia.org/wiki/Plane_(mathematics)
- http://inst.eecs.berkeley.edu/~cs283/sp13/lectures/283-lecture18.pdf
- http://www.gamedev.net/page/resources/_/technical/math-and-physics/quaternion-powers-r1095
- http://www.gamasutra.com/view/feature/3278/
- http://3dgep.com/?p=1815

HCI LAB

Programming Links

- http://pages.cs.wisc.edu/~cs368-2/CppTutorial/NOTES/CLASSES-INTRO.html
- http://www.quantstart.com/articles/Matrix-Classes-in-C-The-Header-File
- http://www.programiz.com/article/c%2B%2B-programming-pattern
- http://stackoverflow.com/questions/564877/point-and-line-class-in-c
- http://www.seasite.niu.edu/CS240/Old_CPP_Notes/lines_class_cpp_program.htm
- http://www.linuxfocus.org/English/March1998/article28.html
- http://www.cs.stanford.edu/~acoates/quaternion.h

HCI LAB

Questions

HCI LAB