



# OSPF



## Routing Protocols and Concepts – Chapter 11

Cisco | Networking Academy®  
Mind Wide Open™

# Objectives

- Describe the background and basic features of OSPF
- Identify and apply the basic OSPF configuration commands
- Describe, modify and calculate the metric used by OSPF
- Describe the Designated Router/Backup Designated Router (DR/BDR) election process in multiaccess networks
- Describe the uses of additional configuration commands in OSPF

# Introduction

	Interior Gateway Protocols				Exterior Gateway Protocols
	Distance Vector Routing Protocols		Link State Routing Protocols		Path Vector
Classful	RIP	IGRP			EGP
Classless	RIPv2	EIGRP	OSPFv2	IS-IS	BGPv4
IPv6	RIPng	EIGRP for IPv6	OSPFv3	IS-IS for IPv6	BGPv4 for IPv6

## In this chapter, you will learn to:

- Describe the background and basic features of OSPF.
- Identify and apply the basic OSPF configuration commands.
- Describe, modify and calculate the metric used by OSPF.
- Describe the Designated Router/Backup Designated Router (DR/BDR) election process in multiaccess networks.
- Employ the `default-information originate` command to configure and propagate a default route in OSPF.

# Introduction to OSPF


## Background of OSPF

- Began in 1987
- 1989 OSPFv1 released in RFC 1131

This version was experimental & never deployed

- 1991 OSPFv2 released in RFC 1247
- 1998 OSPFv2 *updated* in RFC 2328
- 1999 OSPFv3 published in RFC 2740

OSPF Development Timeline



# Introduction to OSPF

## OSPF Message Encapsulation

- OSPF packet type

There exist 5 types

- OSPF packet header

**Contains** - Router ID and area ID **and** Type code for OSPF packet type

- IP packet header

**Contains** - Source IP address, Destination IP address, & Protocol field set to 89

Encapsulated OSPF Message




# Introduction to OSPF

## OSPF Message Encapsulation

- Data link frame header

Contains - Source MAC address and Destination MAC address

Encapsulated OSPF Message



# Introduction to OSPF

## OSPF Packet Types

Type	Packet Name	Description
1	Hello	Discovers neighbors and builds adjacencies between them
2	Database Description (DBD)	Checks for database synchronization between routers
3	Link-State Request (LSR)	Requests specific link-state records from router to router
4	Link-State Update (LSU)	Sends specifically requested link-state records
5	Link-State Acknowledgement (LSAck)	Acknowledges the other packet types


# Introduction to OSPF

## Hello Protocol

- OSPF Hello Packet

- Purpose of Hello Packet


- Discover OSPF neighbors & establish adjacencies
- Advertise guidelines on which routers must agree to become neighbors
- Used by multi-access networks to elect a **designated router** and a **backup designated router**





# Introduction to OSPF

- Hello Packets continued
  - Contents of a Hello Packet
    - router ID of transmitting router
- OSPF Hello Intervals
  - Usually multicast (224.0.0.5)
  - Sent every 30 seconds for NBMA segments
- OSPF Dead Intervals
  - This is the time that must transpire before the neighbor is considered down
  - Default time is 4 times the hello interval



Matching interface values for two routers to form an adjacency

<ul style="list-style-type: none"> <li>Hello Interval</li> <li>Dead Interval</li> <li>Network Type</li> </ul>	}	=	<ul style="list-style-type: none"> <li>Hello Interval</li> <li>Dead Interval</li> <li>Network Type</li> </ul>
---	---	---	---

# Introduction to OSPF

- Hello protocol packets contain information that is used in electing
  - Designated Router (DR)
    - DR is responsible for updating all other OSPF routers
  - Backup Designated Router (BDR)
    - This router takes over DR's responsibilities if DR fails

# Introduction to OSPF

## OSPF Link-state Updates

- Purpose of a Link State Update (LSU)
  - Used to deliver link state advertisements
- Purpose of a Link State Advertisement (LSA)
  - Contains information about neighbors & path costs

LSUs Contain Link-State Advertisements (LSAs)

Type	Packet Name	Description
1	Hello	Discovers neighbors and builds adjacencies between them
2	DBD	Checks for database synchronization between router
3	LSR	Requests specific link-state records from router to router
4	LSU	Sends specifically requested link-state records
5	LSAck	Acknowledges the other packet types

- The acronyms LSA and LSU are often used interchangeably.**
- An LSU contains one or more LSAs.**
- LSAs contain route information for destination networks.**
- LSA specifics are discussed in CCNP.**


LSA Type	Description
1	Router LSAs
2	Network LSAs
3 or 4	Summary LSAs
5	Autonomous System External LSAs
6	Multicast OSPF LSAs
7	Defined for Not-So-Stubby Areas
8	External Attributes LSA for Border Gateway Protocol(BGP)
9,10,11	Opaque LSAs

# Introduction to OSPF

## OSPF Algorithm

- OSPF routers build & maintain link-state database containing LSA received from other routers

- Information found in database is utilized upon execution of Dijkstra SPF algorithm
- SPF algorithm used to create SPF tree
- SPF tree used to populate routing table



# Introduction to OSPF

## Administrative Distance

- Default Administrative Distance for OSPF is 110


**Default Administrative Distances**

Route Source	Administrative Distance
Connected	0
Static	1
EIGRP summary route	5
External BGP	20
Internal EIGRP	90
IGRP	100
<b>OSPF</b>	<b>110</b>
IS-IS	115
RIP	120
External EIGRP	170
Internal BGP	200

# Introduction to OSPF

- OSPF Authentication

- Purpose is to encrypt & authenticate routing information
- This is an interface specific configuration
- Routers will only accept routing information from other routers that have been configured with the same password or authentication information




# Basic OSPF Configuration

## Lab Topology

- Topology used for this chapter

Discontiguous IP addressing scheme

Since OSPF is a classless routing protocol the subnet mask is configured in



# Basic OSPF Configuration

## The router ospf command

- To enable OSPF on a router use the following command

R1(config)#**router ospf process-id**

Process id

- A locally significant number between **1** and **65535**  
-this means it does not have to match other OSPF routers

```
R1 (config) #router ospf 1
R1 (config-router) #
```

```
R2 (config) #router ospf 1
R2 (config-router) #
```

```
R3 (config) #router ospf 1
R3 (config-router) #
```



# Basic OSPF Configuration

- OSPF network command

- Requires entering: **network address**

- wildcard mask** - the inverse of the subnet mask

- area-id** - area-id refers to the OSPF area. OSPF area is a group of routers that share link state information

- Example: Router(config-router)#**network** network-address wildcard-mask **area** area-id

```
R1 (config)#router ospf 1
R1 (config-router) #network 172.16.1.16 0.0.0.15 area 0
R1 (config-router) #network 192.168.10.0 0.0.0.3 area 0
R1 (config-router) #network 192.168.10.4 0.0.0.3 area 0
```

```
R2 (config)#router ospf 1
R2 (config-router) #network 10.10.10.0 0.0.0.255 area 0
R2 (config-router) #network 192.168.10.0 0.0.0.3 area 0
R2 (config-router) #network 192.168.10.8 0.0.0.3 area 0
```

# Basic OSPF Configuration

## ■ Router ID

- This is an IP address used to identify a router
- 3 criteria for deriving the router ID
  - Use IP address configured with OSPF *router-id* command
    - Takes precedence over loopback and physical interface addresses
  - If router-id command not used then router chooses highest IP address of any loopback interfaces
  - If no loopback interfaces are configured then the highest IP address on any active interface is used

# Basic OSPF Configuration

## OSPF Router ID


- Commands used to verify current router ID
  - Show ip protocols
  - Show ip ospf
  - Show ip ospf interface

```

R1#show ip protocols
Routing Protocol is "ospf 1"
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
  Router ID 192.168.10.5
  Number of areas in this router is 1. 1 normal 0 stub 0 nssa

R2#show ip protocols
Routing Protocol is "ospf 1"
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
  Router ID 192.168.10.9
  Number of areas in this router is 1. 1 normal 0 stub 0 nssa

R3#show ip protocols
Routing Protocol is "ospf 1"
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
  Router ID 192.168.10.10
  Number of areas in this router is 1. 1 normal 0 stub 0 nssa
    
```



# Basic OSPF Configuration

## OSPF Router ID

```
R1 (config) #interface loopback 0
R1 (config-if) #ip add 10.1.1.1 255.255.255.255
```

- Router ID & Loopback addresses
  - Highest loopback address will be used as router ID if router-id command isn't used
  - Advantage of using loopback address
    - the loopback interface cannot fail → OSPF stability
- The OSPF router-id command
  - Introduced in IOS 12.0
  - Command syntax
    - Router(config)#router ospfprocess-id
    - Router(config-router)#router-idip-address
- Modifying the Router ID
  - Use the command Router#clear ip ospf process

# Basic OSPF Configuration

## Verifying OSPF

- Use the show ip ospf command to verify & trouble shoot OSPF networks

Command will display the following:

- Neighbor adjacency
  - No adjacency indicated by -
    - Neighboring router's Router ID is not displayed
    - A state of **full** is not displayed
  - Consequence of no adjacency-
    - No link state information exchanged
    - Inaccurate SPF trees & routing tables

```
R1#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
10.3.3.3	1	FULL/ -	00:00:30	192.168.10.6	Serial0/0/1
10.2.2.2	1	FULL/ -	00:00:33	192.168.10.2	Serial0/0/0

# Basic OSPF Configuration

## Verifying OSPF - Additional Commands

Command	Description
Show ip protocols	Displays OSPF process ID, router ID, networks router is advertising & administrative distance
Show ip ospf	Displays OSPF process ID, router ID, OSPF area information & the last time SPF algorithm calculated
Show ip ospf interface	Displays hello interval and dead interval

# Basic OSPF Configuration

## Examining the routing table

- Use the show ip route command to display the routing table
  - An “O’ at the beginning of a route indicates that the router source is OSPF
  - Note OSPF does not automatically summarize at major network boundaries

```

R1#show ip route

Codes: <some code output omitted>
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

Gateway of last resort is not set

    192.168.10.0/30 is subnetted, 3 subnets
C       192.168.10.0 is directly connected, Serial0/0/0
C       192.168.10.4 is directly connected, Serial0/0/1
O       192.168.10.8 [110/128] via 192.168.10.2, 14:27:57, Serial0/0/0
    172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks
O       172.16.1.32/29 [110/65] via 192.168.10.6, 14:27:57, Serial0/0/1
C       172.16.1.16/28 is directly connected, FastEthernet0/0
    10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
O       10.10.10.0/24 [110/65] via 192.168.10.2, 14:27:57, Serial0/0/0
C       10.1.1.1/32 is directly connected, Loopback0

```

# OSPF Metric

- OSPF uses **cost** as the metric for determining the best route
  - The best route will have the lowest cost
  - Cost** is based on bandwidth of an interface
    - Cost is calculated using the formula
 
$$10^8 / \text{bandwidth}$$
  - Reference bandwidth
    - defaults to 100Mbps
    - can be modified using
    - **auto-cost reference-bandwidth** command


Interface Type	$10^8/\text{bps} = \text{Cost}$
Fast Ethernet and faster	$10^8/100,000,000 \text{ bps} = 1$
Ethernet	$10^8/10,000,000 \text{ bps} = 10$
E1	$10^8/2,048,000 \text{ bps} = 48$
T1	$10^8/1,544,000 \text{ bps} = 64$
128 kbps	$10^8/128,000 \text{ bps} = 781$
64 kbps	$10^8/64,000 \text{ bps} = 1562$
56 kbps	$10^8/56,000 \text{ bps} = 1785$



# OSPF Metric

- COST of an OSPF route

Is the accumulated value from one router to the next



```

R1#show ip route
Codes: <some code output omitted>
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area


<route output omitted.
O      10.10.10.0/24 [110/65] via 192.168.10.2, 14:27:57, Serial0/0/0
    
```

**Accumulated Cost = 65**

# OSPF Metric

- Usually the actual speed of a link **is different** than the default bandwidth
  - This makes it imperative that the bandwidth value reflects link's actual speed
    - Reason: so routing table has best path information
- The **show interface** command will display interface's bandwidth
  - Most serial link default to 1.544Mbps

Differences Between Default and Actual Bandwidth



```

R1#show interface serial 0/0/0
Serial0/0/0 is up, line protocol is up
Hardware is GT96K Serial
Description: Link to R2
Internet address is 192.168.10.1/30
MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Default Bandwidth = 1544 kbps
Actual Bandwidth = 64 kbps
    
```

# Basic OSPF Configuration

## Modifying the Cost of a link

- Both sides of a serial link should be configured with the same bandwidth

–Commands used to modify bandwidth value

- Bandwidth** command


–Example: Router(config-if)#**bandwidth***bandwidth-kbps*

- ip ospf cost** command – allows you to directly specify interface cost


–Example:R1(config)#interface serial 0/0/0

R1(config-if)#ip ospf cost 1562

```
R1(config)#inter serial 0/0/0
R1(config-if)#bandwidth 64
R1(config-if)#inter serial 0/0/1
R1(config-if)#bandwidth 256
R1(config-if)#end
R1#show ip ospf interface serial 0/0/0
Serial0/0 is up, line protocol is up
 Internet Address 192.168.10.1/30, Area 0
 Process ID 1, Router ID 10.1.1.1, Network Type POINT_TO_POINT, Cost: 1562
 Transmit Delay is 1 sec, State POINT_TO_POINT,
 <output omitted>
```



```
R1(config)#inter serial 0/0/0
R1(config-if)#ip ospf cost 1562
R1(config-if)#end
R1#show ip ospf interface serial 0/0/0
Serial0/0 is up, line protocol is up
 Internet Address 192.168.10.1/30, Area 0
 Process ID 1, Router ID 10.1.1.1, Network Type POINT_TO_POINT, Cost: 1562
 Transmit Delay is 1 sec, State POINT_TO_POINT,
 <output omitted>
```



# Basic OSPF Configuration

## Modifying the Cost of the link

- Difference between bandwidth command & the ip ospf cost command
  - **ip ospf cost** command
    - Sets cost to a specific value
  - **Bandwidth** command
    - Link cost is calculated

### Equivalent Commands

#### bandwidth Commands

```

Router R1
R1(config)#interface serial 0/0/0
R1(config-if)#bandwidth 64

R1(config)#interface serial 0/0/1
R1(config-if)#bandwidth 256

Router R2
R2(config)#interface serial 0/0/0
R2(config-if)#bandwidth 64

R2(config)#interface serial 0/0/1
R2(config-if)#bandwidth 128

Router R3
R3(config)#interface serial 0/0/0
R3(config-if)#bandwidth 256

R3(config)#interface serial 0/0/1
R3(config-if)#bandwidth 128
    
```

#### ip ospf cost Commands

```

Router R1
R1(config)#interface serial 0/0/0
R1(config-if)#ip ospf cost 1562

R1(config)#interface serial 0/0/1
R1(config-if)#ip ospf cost 390

Router R2
R2(config)#interface serial 0/0/0
R2(config-if)#ip ospf cost 1562

R2(config)#interface serial 0/0/1
R2(config-if)#ip ospf cost 781

Router R3
R3(config)#interface serial 0/0/0
R3(config-if)#ip ospf cost 390


R3(config)#interface serial 0/0/1
R3(config-if)#ip ospf cost 781
    
```

# OSPF and Multiaccess Networks

## Challenges in Multiaccess Networks

- OSPF defines five network types:
  - Point-to-point
  - Broadcast Multiaccess
  - Nonbroadcast Multiaccess (NBMA)
  - Point-to-multipoint
  - Virtual links


OSPF Network Types Used in the Topology



# OSPF in Multiaccess Networks

- 2 challenges presented by multiaccess networks
  - Multiple adjacencies
  - Extensive LSA flooding

Number of Adjacencies Grows Exponentially



Number of Adjacencies =  $n(n-1)/2$   
 n = number of routers  
 Example: 5 routers  $(5 - 1)/2 = 10$  adjacencies

Routers	Adjacencies
$n$	$n(n-1)/2$
5	10
10	45
20	190
100	4,950


# OSPF in Multiaccess Networks

- Extensive flooding of LSAs

For every LSA sent out there must be an acknowledgement of receipt sent back to transmitting router.

consequence: lots of bandwidth consumed and chaotic traffic


LSA Flooding Scenario




# OSPF in Multiaccess Networks

- Solution to LSA flooding issue is the use of
  - Designated router (DR)
  - Backup designated router (BDR)
- DR & BDR selection
  - Routers are elected to send & receive LSA
- Sending & Receiving LSA
  - DR others send LSAs via multicast 224.0.0.6 to DR & BDR
  - DR forward LSA via multicast address 224.0.0.5 to all other routers

Adjacencies are formed with DR and BDR only.  
LSAs are sent to the DR. BDR listens.



DR sends out any LSAs to all other routers.






# OSPF in Multiaccess Networks

## DR/BDR Election Process

- DR/BDR elections **DO NOT** occur in point to point networks


Point-to-Point Three Router Topology



# OSPF in Multiaccess Networks

- DR/BDR elections **will take place on multiaccess networks** as shown below

Multiaccess Three Router Topology




Notice that routers are now communicating via LAN interfaces.

# OSPF in Multiaccess Networks

## Criteria for getting elected DR/BDR

- DR:** Router with the **highest** OSPF interface **priority**.
- BDR:** Router with the **second highest** OSPF interface **priority**.
- If OSPF interface **priorities are equal**, the **highest router ID** is used to break the tie.



```
RouterA#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.31.33	1	FULL/DR	00:00:39	192.168.1.3	FastEthernet0/0
192.168.31.22	1	FULL/BDR	00:00:36	192.168.1.2	FastEthernet0/0

```
RouterB#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.31.33	1	FULL/DR	00:00:34	192.168.1.3	FastEthernet0/0
192.168.31.11	1	FULL/DROTHER	00:00:38	192.168.1.1	FastEthernet0/0

```
RouterC#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.31.22	1	FULL/BDR	00:00:35	192.168.1.2	FastEthernet0
192.168.31.11	1	FULL/DROTHER	00:00:32	192.168.1.1	FastEthernet0

Priority is equal at the default value of 1.

```
RouterA#show ip ospf interface fastethernet 0/0
```

```
FastEthernet0/0 is up, line protocol is up
  Internet Address 192.168.1.1/24, Area 0
  Process ID 1, Router ID 192.168.31.11, Network Type BROADCAST, Cost: 1
  Transmit Delay is 1 sec, State DROTHER, Priority 1
  Designated Router (ID) 192.168.31.33, Interface address 192.168.1.3
  Backup Designated router (ID) 192.168.31.22, Interface address 192.168.1.2
  Timer intervals configured, Hello 10, Dead 40, Wait 40, Retransmit 5
    oob-resync timeout 40
    Hello due in 00:00:06
  Supports Link-local Signaling (LLS)
  Index 1/1, flood queue length 0
  Next 0x0 (0)/0x0 (0)
  Last flood scan length is 0, maximum is 1
  Last flood scan time is 0 msec, maximum is 0 msec
  Neighbor Count is 2, Adjacent neighbor count is 2
    Adjacent with neighbor 192.168.31.22 (Backup Designated Router)
    Adjacent with neighbor 192.168.31.33 (Designated Router)
  Suppress hello for 0 neighbor(s)
```

# OSPF in Multiaccess Networks

- Timing of DR/BDR Election
  - Occurs as soon as 1<sup>st</sup> router has its interface enabled on multiaccess network
    - When a DR is elected it remains as the DR until one of the following occurs
      - The DR fails.
      - The OSPF process on the DR fails.
      - The multiaccess interface on the DR fails.


# OSPF in Multiaccess Networks

- Manipulating the election process
  - If you want to influence the election of DR & BDR then do one of the following
    - Boot up the DR first, followed by the BDR, and then boot all other routers,
    - OR
    - Shut down the interface on all routers, followed by a **no shutdown** on the DR, then the BDR, and then all other routers.

# OSPF in Multiaccess Networks

## OSPF Interface Priority

- Manipulating the DR/BDR election process continued
  - Use the `ip ospf priority interface` command.
  - Example: Router(config-if)#`ip ospf priority {0 - 255}`
    - Priority number range 0 to 255
      - 0 means the router cannot become the DR or BDR
      - 1 is the default priority value



```
RouterA#show ip ospf interface fastethernet 0/0
FastEthernet0/0 is up, line protocol is up
Internet Address 192.168.1.1/24, Area 0
Process ID 1, Router ID 192.168.31.11, Network Type BROADCAST, Cost: 1
Transmit Delay is 1 sec, State DROTHER, Priority 1
Designated Router (ID) 192.168.31.33, Interface address 192.168.1.3
Backup Designated router (ID) 192.168.31.22, Interface address 192.168.1.2
Timer intervals configured, Hello 10, Dead 40, Wait 40, Retransmit 5
oob-resync timeout 40
.....
```

# More OSPF Configuration

## Redistributing an OSPF Default Route

- Topology includes a link to ISP

- Router connected to ISP

- Called an autonomous system border router

- Used to propagate a default route


- Example of static default route

R1(config)#**ip route 0.0.0.0 0.0.0.0 loopback 1**

- Requires the use of the **default-information originate** command

- Example of default-information originate command


R1(config-router)#**default-information originate**



# More OSPF Configuration

## Fine-Tuning OSPF

- Since link speeds are getting faster it may be necessary to change reference bandwidth values
  - Do this using the **auto-cost reference-bandwidth** command
  - Example:
    - **R1(config-router)#auto-cost reference-bandwidth 10000**



```

R1(config-if)#router ospf 1
R1(config-router)#auto-cost reference-bandwidth ?
<1-4294967> The reference bandwidth in terms of Mbits per second

R1(config-router)#auto-cost reference-bandwidth 10000
% OSPF: Reference bandwidth is changed.

R2(config-if)#router ospf 1
R2(config-router)#auto-cost reference-bandwidth 10000
% OSPF: Reference bandwidth is changed.
Please ensure reference bandwidth is consistent across all routers.

R3(config-if)#router ospf 1
R3(config-router)#auto-cost reference-bandwidth 10000
% OSPF: Reference bandwidth is changed.
Please ensure reference bandwidth is consistent across all routers.
    
```



# More OSPF Configuration

## Fine-Tuning OSPF

- Modifying OSPF timers

- Reason to modify timers

- Faster detection of network failures

- Manually modifying Hello & Dead intervals

- Router(config-if)#**ip ospf hello-interval seconds**

- Router(config-if)#**ip ospf dead-interval seconds**

- Point to be made

- Hello & Dead intervals must be the same between neighbors

```
R1 (config)#interface serial 0/0/0
R1 (config-if)#ip ospf hello-interval 5
R1 (config-if)#ip ospf dead-interval 20
R1 (config-if)#end

<Wait 20 seconds for IOS message>
```

# Summary

- RFC 2328 describes OSPF link state concepts and operations
- OSPF Characteristics
  - A commonly deployed link state routing protocol
  - Employs **DRs** & **BDRs** on multi-access networks
    - DRs & BDRs are elected
    - DR & BDRs are used to transmit and receive LSAs
  - Uses 5 packet types:
    - 1: HELLO**
    - 2: DATABASE DESCRIPTION**
    - 3: LINK STATE REQUEST**
    - 4: LINK STATE UPDATE**
    - 5: LINK STATE ACKNOWLEDGEMENT**

# Summary

- OSPF Characteristics

- Metric = cost

- Lowest cost = best path

- Configuration

- Enable OSPF on a router using the following command

- R1(config)#**router ospf process-id**

- use the network command to define which interfaces will participate in a given OSPF process

- Router(config-router)#**network network-address wildcard-mask area area-id**

# Summary

- Verifying OSPF configuration
  - Use the following commands
    - show ip protocol
    - show ip route
    - show ip ospf interface
    - show ip ospf neighbor

