



# Module 16: Troubleshoot Static and Default Routes

Switching, Routing and Wireless Essentials v7.0  
(SRWE)




# Module Objectives

**Module Objective:** Troubleshoot static and default route configurations.

Topic Title	Topic Objective
Packet Processing with Static Routes	Explain how a router processes packets when a static route is configured.
Troubleshoot IPv4 Static and Default Route Configuration	Troubleshoot common static and default route configuration issues.

# Static Routes and Packet Forwarding

- **PC1** addresses a packet to **PC3** and sends it to the default gateway address.
- When the packet arrives on the **R1** G0/0/0 interface, R1 decapsulates the packet and searches the routing table for a matching destination network entry.




If the destination IP address:

- Matches a static route entry, **R1** will use the static route to identify the **next-hop** IP address or exit interface.
- Does not match a specific route to the destination network, then **R1** will use the **default static** route (if configured).
- Does not match a route table entry, then **R1** will **drop** the packet and send an ICMP message back to the source (i.e., PC1).

# Static Routes and Packet Forwarding (Cont.)


Assuming **R1** matched a routing table entry, it encapsulates the packet in a **new frame** and forwards it out of interface S0/1/0 to R2.

- **R2** receives the packet on its S0/1/0 interface.
- It decapsulates and processes the packet the same way **R1** did.
- When **R2** finds a match in the routing table, it uses the identified **next-hop** IP address or exit interface and sends the packet out of its interface S0/1/1 towards R3.



# Static Routes and Packet Forwarding (Cont.)

- **R3** receives the packet, decapsulates it, and searches the routing table for a match.
- The destination IP address of **PC3** matches the directly connected G0/0/0 interface. Therefore, **R3** searches the **ARP table** for the Layer 2 MAC address of **PC3**.
- If no ARP entry exists, then **R3** sends an **ARP request** out of the G0/0/0 interface.



- **PC3** responds with an **ARP reply** containing its MAC address.
- **R3** encapsulates the packet in a new frame and uses the **PC3** MAC address as the destination MAC address and the G0/0/0 MAC address as the source MAC address.
- The frame is **forwarded out** of interface G0/0/0 and **PC3** receives and processes it accordingly.

# 16.2 Troubleshoot IPv4 Static and Default Route Configuration

# Network Changes

Networks fail for a number of reasons:

- An **interface can fail**
- A service provider **drops a connection**
- Links can become **oversaturated**
- An administrator may enter a **wrong configuration**.

Network administrators are responsible for pinpointing and solving the problem.

To efficiently find and solve these issues, it is advantageous to be intimately familiar with **tools to help isolate** routing problems quickly.

# Common Troubleshooting Commands


Command	Description
<code>ping</code>	<ul style="list-style-type: none"><li>• Verify Layer 3 connectivity to destination.</li><li>• Extended pings provide additional options.</li></ul>
<code>tracert</code>	<ul style="list-style-type: none"><li>• Verify path to destination network.</li><li>• It uses ICMP echo reply messages to determine the hops to the destination.</li></ul>
<code>show ip route</code>	<ul style="list-style-type: none"><li>• Displays the routing table.</li><li>• Used to verify route entries for destination IP addresses.</li></ul>
<code>show ip interface brief</code>	<ul style="list-style-type: none"><li>• Displays the status of device interfaces.</li><li>• Used to verify the operational status and IP address of an interface.</li></ul>
<code>show cdp neighbors</code>	<ul style="list-style-type: none"><li>• Displays a list of directly connected Cisco devices.</li><li>• Also used to validate Layer 1 and 2 connectivity.</li></ul>



# Solve a Connectivity Problem

Connectivity from PC1 to PC3 fails.

- Extended pings from the R1 G0/0/0 interface to PC3 fail.
- Pings from R1 (i.e., S0/1/0 interface) to R2 are successful.
- Pings from R1 (i.e., S0/1/0 interface) to R3 are successful.




- R2 routing table reveals the problem and the incorrect static route is removed.
- A new static route solves the problem.
- `ip route 172.16.3.0 255.255.255.0 172.16.2.1`

```
R2# show ip route | begin Gateway
Gateway of last resort is not set
  172.16.0.0/16 is variably subnetted, 5 subnets, 2 masks
C       172.16.1.0/24 is directly connected, GigabitEthernet0/0/0
L       172.16.1.1/32 is directly connected, GigabitEthernet0/0/0
C       172.16.2.0/24 is directly connected, Serial0/1/0
L       172.16.2.2/32 is directly connected, Serial0/1/0
S       172.16.3.0/24 [1/0] via 192.168.1.1
  192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.1.0/24 is directly connected, Serial0/1/1
L       192.168.1.2/32 is directly connected, Serial0/1/1
S       192.168.2.0/24 [1/0] via 192.168.1.1
R2#
```


# Opakování: IP zátěž v těle rámce

## An Ethernet Frame – 7 fields




Field sizes in bytes. Preamble and StartFD are not counted in frame size. Frame size is 64 to 1518 bytes (VLAN's 1522b).

# FIB (Forwarding Information Base) a Adjacency table



# Implementace FIB v TCAM, Adjacency table je implementována v RAM



# 16.3 Module Practice and Quiz

adhere

# Packet Tracer – Troubleshoot Static and Default Routes

In this activity you will troubleshoot and static and default routes and repair any errors that you find.

- Troubleshoot IPv4 static routes.
- Troubleshoot IPv6 static routes.
- Configure IPv4 static routes.
- Configure IPv4 default routes.
- Configure IPv6 static routes.

# Lab - Troubleshoot Static and Default Routes

In this lab, you will complete the following objectives:

- Evaluate Network Operation.
- Gather information, create an action plan, and implement corrections.

# What did I learn in this module?

- A host sends a packet to another host and sends it to the default gateway address.
- When the packet arrives on a router interface, it decapsulates the packet and searches the routing table for a matching destination network entry.
- If the destination IP address:
  - Matches a static route entry, the router will use the static route to identify the next hop IP address or exit interface.
  - Does not match a specific route to the destination network, then the router will use the default static route (if configured).
  - Does not match a route table entry, then the router will drop the packet and send an ICMP message back to the source.
- If the router matched a routing table entry, then the router encapsulates the packet and forwards it out of the appropriate interface.
- The packet is forwarded from router to router until it reaches its destination network.



## What did I learn in this module? (Cont.)

- When the packet reaches the destination network, that router will search the routing table for a match.
- When the destination IP address matches a directly connected Ethernet interface, the router searches the ARP table for the Layer 2 MAC address of the destination IP address.
- If no ARP entry exists, the router sends an ARP request out of the Ethernet interface
- The destination host responds with an ARP reply containing its MAC address.
- The router then encapsulates the packet in a new frame. It uses the MAC address of the destination host as the frame destination MAC address, and the MAC address of the router Ethernet interface as the source MAC address in the frame.
- The frame is forwarded out of the appropriate interface.
- The packet arrives on the network interface card (NIC) interface of destination host and is processed accordingly.

## What did I learn in this module? (Cont.)

Common IOS troubleshooting commands to troubleshoot IPv4 Static and default routes include:

- **ping**
- **tracert**
- **show ip route**
- **show ip interface brief**
- **show cdp neighbors detail**

