
## **Temporal canals**

1. <u>Canalis nervi facialis</u> – <u>begins</u> at the bottom of internal acoustic meatus and <u>ends</u> in stylomastoid foramen; (facial nerve)

The bottom of internal acoustic meatus:



- The canal has three parts:
- 1. After the canal began at bottom of internal acoustic meatus it goes upright to the longitudinal axis of pyramis (there goes out the branch called greater petrosal nerve).
- 2. Near the greater petrosal nerve hiatus it turns to the lateral side and goes at the medial wall of middle ear cavity. Then the canal is located at the dorsal wall of middle ear cavity. (paralel with the longitudinal axis)
- 3. The last part of facial canal turns downwards and ends in stylomastoid foramen.

<u>Canaliculus chordae tympani</u> – chorda tympani is branch of facial nerve and <u>begins</u> in the 3<sup>rd</sup> part of facial canal and <u>ends</u> in petrotympanic fissure; (chorda tympani)


<u>Carotid canal (canalis caroticus)</u> – it <u>starts</u> at inferior surface of pyramis in external aperture of carotid canal;- it has sigmoid shape (because the blood pressure is too high for nerve tissue, it could cause demage of brain. So that the function of this canal is to reduce blood pressure before the blood enters to the brain);-<u>ends</u> at the top of pyramis (internal aperture of carotid canal); (internal carotid artery)

<u>Caroticotympanic canaliculi (canaliculi caroticotympanici)</u> – they <u>start</u> within the carotid canal (first curvature) and end in the middle ear cavity; (carotycotympanic nerves)

<u>Mastoid canaliculus (canaliculus mastoideus) - starts</u> at the bottom of jugular fossa and <u>ends</u> in tympanomastoid fissure; (auricular branch of vagus nerve)

<u>Tympanic canaliculus (canaliculus tympanicus)</u> - <u>starts</u> at the bottom of fossula petrosa (between the jugular fossa and external aperture of carotid canal), it goes through the middle ear cavity and <u>ends</u> in lesser petrosal hiatus; (tympanic nerve→lesser petrosal nerve)

<u>Musculotubarius canal (canalis musculotubarius)</u> – begins at the top of pyramis more ventraly than the internal aperture of carotid canal; is devided by the septum canalis musculotubarii into two levels: upper (semicanalis musculi tensoris tympani) and lower (semicanalis tubae auditivae); ends in middle ear cavity;(tensor tympani muscle and Eustachian tube)



<u>Vestibular canaliculus (canaliculus vestibuli)</u> – this canaliculus is for endolymfa drainage;it <u>starts</u> in the inner ear and ends at the posterior surface of pyramis in external aperture of aqueductus vestibuli

<u>Cochlear canaliculus (canaliculus cochleae) -</u> this canaliculus is for perilymfa drainage; it <u>starts</u> in the inner ear and <u>ends</u> in external aperture of cochlear canaliculus