• Class I.

Pit and fissure caries

Class II. Proximal surfaces in premolars and molars



• Class III.

Proximal surfaces of incisors and canines without lost any part if incisal edge

 Class IV.
 Proximal surfaces of incisors and canines with lost an incisal ridge



• Class V. cervical lesions



Preparation of cavities Basic rules

Access to the cavity **Outlines – cavosurface margin (extention for** prevention) Principles of retention **Principles of resistance Excavation of carious dentin Preparation of borders** – finishing Control

Protection of dentin wound

Dentin wound should be covered – protection of dental pulp against irritation
Physicial
-thermal
-osmotic
Chemical
Combination

Protection of dentin wound

Isolation Filling (small cavities)

Base (moderate – large cavities- depth 2mm and more approx.)


Adhesive systems (composite materials)

Filling

 Filling replaces lost hard dental tissue anatomically and functionally

 Always different properties in comparison to hard dental tissues.

Base is made usually of zinkoxidphosphate cement It is placed only on pulpal wall




Preparation of the cavity I.st class acc. to Black

- Cavities in fissures and pits
- (Occlusal surfaces of premolars and molars and in f. coeca)

- F. Coeca: buccal surfaces of lower molars,
- Palatal surfaces of lower molars, palatal surfaces of upper incisors (mostly lateral)

Morphology of fissures

Biofilm







All pit and fissure restorations (fillings)

They are assigned in to three groups. R. on <u>occlusal surface of premolars and molars</u>

R. in foramina coeca – usually on <u>occlusal two thirds</u> of the facial and lingual surfaces of molars.


R.on lingual surface of maxillary incisors.

Materials: Amalgam, composite. Amalgam: Pertinent material qualities and propeties

Strength Longevity Easy of use Clinically proven sucess

Access to the cavity


From the occlusal surface using the fissure bur (or diamond burs, see below).




Cavosurface margin


 Ideal outline includes all occlusal pits and fissures. If crista transversa (1st lower premolar)or obliqua (1st and 2nd upper molar)are not affected, it is strongly recommended no to prepare them.

 Cavosurface margin is located in the middle of the distanc between the bottom of the fissure and the cusp




Cavosurface margin is in ½ distance between bottom of the fissure and the cuso





Premolars

Crista transversa Lower P1






Retention principles


- Prepare the box the bottom is in dentin
- Undercuts can be prepared, the proximal ridges must not be weakened!

Retention principles


• Box in dentin



Box (remember rounded edges)




Box with undercut



Resistance principles

- Box space for amalgam 1,5 2 mm
- Keep the facial and lingual margin extensions as minimal as possible between the central groove and the cusp tips. Max 1/2
- Extending the outline to include fissures, thereby placing the margins on relatively smooth sound tooth structure.
- Minimally extending into the marginal ridge without removing dentinal support.
- Never leave the enamel undermined
- All corners are round, the bottom smooth.

TT





Removal of carious, infected, dentin

 Spoon excavator or a slowly revolving, round carbid bur of appropriate size.



The pulpal wall and pulp chamber






Finishing and polishing


• Fine grit diamond bur.

Final control

• Wash and dry the cavity

Check the praparation in good illumination





Preparation is limited on the caries lesion 1,5 mm deep Undercuts can be prepared

If the caries undermined the occlusa enamel, prepare the cavity on the occlusal surface.

