

Composites in posterior teeth

All pit and fissure restorations.

They are assigned in to three groups.

R. on occlusal surface of premolars and molars

R. in foramina coeca – usually on occlusal two thirds of the facial and lingual surfaces of molars.

R.on lingual surface of maxillary incisors.

Longevity of fillings

T
r
v
a
n
l
i
v
o
i
s
t



Indications

- Moderate to large restorations
- Restorations that are not in highly aesthetics areas
- Restorations that have heavy occlusal contacts
- Restorations that cannot be well isolated
- Restorations that extend onto the root surface
- Foundations
- Abutment teeth for removable partial dentures
- Temporary or caries control restorations.

Contraindications

- Aesthetically prominent areas of posterior teeth
- Small moderate classes I. that can be well isolated

Materials: Amalgam, composite.

Amalgam:

Pertinent material qualities and properties

Strength

Longevity

Ease of use

Clinically proven success

Clinical technique

- From the occlusal surface using the fissure bur (or diamond burs, see below).

Outline

- Ideal outline includes all occlusal pits and fissures. If crista transversa or obliqua are not affected, it is recommended not to prepare them.

Resistance principles

- Keep the facial and lingual margin extensions as minimal as possible between the central groove and the cusp tips.
- Extending the outline to include fissures, thereby placing the margins on relatively smooth sound tooth structure.
- Minimally extending into the marginal ridge without removing dentinal support.
- Eliminating a weak wall of enamel by joining two outlines that come close together
- Enamel.
 - Never leave the enamel undermined
- All corners are round, the bottom smooth.

Retention principles

- Prepare the box – the bottom is in dentin
- Undercuts can be prepared, the proximal ridges must not be weakened!

Removal of carious, infected, dentin and remaining defective enamel.

- Spoon excavator or a slowly revolving , round carbid bur of appropriate size.

Indications

- Aesthetically prominent areas of posterior teeth
- Small - moderate classes I. that can be well isolated
- Good level of oral hygiene is necessary

Contraindications

- Moderate to large restorations
- Restorations that are not in highly aesthetics areas
- Restorations that have heavy occlusal contacts
- Restorations that cannot be well isolated
- Restorations that extend onto the root surface
- Abutment teeth for removable partial dentures
- Temporary or caries control restorations.

Materials: Amalgam, composite.

Amalgam:

Pertinent material qualities and properties

Strength

Longevity

Ease of use

Clinically proven success

Clinical technique

- From the occlusal surface using the fissure bur (or diamond burs)

Outline


- Outline includes the caries lesion only

Retention principles


- Prepare the box or deep dish – the bottom is in dentin
- Do not prepare any undercuts!
- Do not bevel enamel, finish the border with diamond bur inly.

Removal of carious, infected, dentin and remaining defective enamel.


- Spoon excavator or a slowly revolving , round carbid bur of appropriate size.



Polymerization shrinkage




Polymerization shrinkage



C - factor

Surface of adhesion/free surface of the filling




1/1 and less is optimal




5




2




1






Monomer \longrightarrow Polymer

Polymerní síť




Pre -gel
Gel point
Post -gel




Chemicky iniciovaný kompozit

42µm

43µm





Forces of polymerization shrinkage depend on

- Composite material (content of filler)
- Geometry of the cavity (C-factor)
- Placement of the composite
- Mode of polymerization

Forces of polymerization shrinkage depend on (polymerization stress)

Composite material (content of filler)


High content of the filler causes bigger stress

Flowable composites – low stress


Forces of polymerization shrinkage
depend on

Geometry of the cavity (C-factor)

Polymerization shrinkage




Polymerization shrinkage



C - factor

Surface of adhesion/free surface of the filling



1/1 and less is optimal




5



2





1



Forces of polymerization shrinkage depend on

- Placement of the composite:
- *Create the first layer thin, flowable can be used*
- *Place th material in increments with respect of the C-factor of each layer*

Placement of the material




Forces of polymerization shrinkage depend on

- Mode of polymerization

Phases

- Pre-gel
- G-point
- Post -gel




Light

Polymerization

Monomer → Polymer

Pre gel phase should be long – soft start !!!!




Pre -gel

Gel

Post -gel


Marginal adaptation

- Placement of composite material
- Dry operating field
- Adhesive systems



Flow materiály - význam

1. **Vyrovnání zátěže**
(protistresové vlastnosti)
2. **Vyblokování podsekřivin**
3. **Adaptace ke stěnám**
4. **Estetické důvody**
5. **Ochrana adheziva**




Temperovaný kompozit

C-faktor

= konfigurační faktor

Plocha adheze / volný povrch výplně



neprůzračný C-faktor

Adhesives

- Acid etching technique
- Selfetching adhesive systems

Adhesives

- Acid etching technique

Etching

Washing

Priming Bonding

Adhesives

- Selfetching adhesive systems

Priming


Bonding

Adhesives

- Active and passive bonding

Active – rubbing with microbrush

Passive – without any rubbing



ISI


LEI

5.0kV

X5,000

1 μ m


WD 7.7mm



ISI

LEI

5.0kV



ISI


LEI

5.0kV

X2,000

10μm

WD 7.9mm



ISI


LEI

5.0kV


X2,000

10 μ m


WD 7.7mm



ISI LEI 5.0kV X5,000



ISI LEI 5.0kV X2,000 10µm WD 7.5mm



ISI


LEI

5.0kV

X2,000

10µm

WD 9.8mm



ISI



SEI

5.0kV

X55,000

100nm

WD 8.6mm



ISI


LEI

5.0kV

X6,000

1 μ m

WD 9.0mm



ISI



LEI


5.0kV


X2,000

10 μ m


WD 8.6mm









Adhesive preparation in a fissure




Adhesive preparation



Preparation of enamel borders






Next to cusp
50-60°,


Cervical borders

In enamel




Cervical borders

In dentin




No bevel


Interproximal borders



Preparation technique




probability of damaging adjacent tooth: 70-100%



wrong preparation angle

Oscillating instruments






Composite filling class II. Contact point



Contact point
Contact area



Class II. and contact point

■ Matrix band + matrix retainer

- Metal band
- Plastic band (polyester)

Without matrix retainer

■ Sectional matrices with separator


































Adhezivní slotová preparace



Approximal Caries






Approximal Caries






Tunnel preparation










Success?



Low caries risk
Special small instruments
Magnification
BW post op





